

Adobe® Premiere® 6.0



User Guide



© 2000 Adobe Systems Incorporated. All Rights Reserved. Patent pending.

All PhotoDisc images: © 1997 PhotoDisc, Inc.

This manual, as well as the software described in it, is furnished under license and may only be used or copied in accordance with the terms of such license. The information in this manual is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Adobe Systems Incorporated. Adobe Systems Incorporated assumes no responsibility or liability for any errors or inaccuracies that may appear in this book.

Except as permitted by such license, no part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of Adobe Systems Incorporated.

Please remember that existing movies, sounds, or images that you may want to use in your project may be protected under copyright law. The unauthorized incorporation of such material into your new work could be a violation of the rights of the copyright owner. Please be sure to obtain any permission required from such authors.

Adobe, the Adobe Logo, Adobe Premiere, After Effects, Classroom in a Book, Illustrator, PageMaker, Photoshop, and PostScript are trademarks of Adobe Systems Incorporated, registered in certain jurisdictions. Apple, Macintosh, Power Macintosh, Mac OS, FireWire, and QuickTime are registered trademarks of Apple Computer, Inc., registered in the U.S. and other countries. QuickTime and the QuickTime logo are trademarks used under license. PowerPC is a trademark of International Business Machines Corporation. DirectShow is a trademark of and DirectX, Microsoft, MS-DOS, Video for Windows, Windows, and Windows NT are registered trademarks of Microsoft Corporation in the U.S. and/or other countries. All other trademarks are the property of their respective owners.

Contains implementation of the LZW algorithm licensed under U.S. Patent No. 4,558,302.

QuickHelp™ is licensed from Altura Software, Inc. End-User is prohibited from taking any action to derive a source code equivalent of QuickHelp, including reverse assembly or reverse compilation.

Written and designed at Adobe Systems Incorporated, 345 Park Avenue, San Jose, CA 95110-2704, USA

Adobe Systems Europe Limited, Adobe House, 5 Mid New Cultins, Edinburgh EH11 4DU, Scotland, United Kingdom

Adobe Systems Co., Ltd., Yebisu Garden Place Tower, 4-20-3 Ebisu, Shibuya-ku, Tokyo 150, Japan

For defense agencies: Restricted Rights Legend. Use, reproduction or disclosure is subject to restrictions set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at 252.227-7013.

For Civilian agencies: Restricted Rights Legend. Use, reproduction or disclosure is subject to restrictions set forth in subparagraphs (a) through (d) of the commercial Computer Software Restricted Rights clause at 52.227-19 and the limitations set forth in Adobe's standard commercial agreement for this software. Unpublished rights reserved under the copyright laws of the United States.

Printed in the USA.

Part number: 90012291 (12/00)

Contents

Introduction

Registration	1
Installing Adobe Premiere	1
Learning Premiere	1
Using Web resources	3
Other learning resources	5
Customer support	5

An Overview of Adobe Premiere

Setting up your workspace	8
Starting a project	10
Work area overview	12
Using tools and palettes	13
Looking at the Project window	14
Looking at the Timeline window	16
Looking at the Monitor window	18
Acquiring source material	21
Adding clips to the Timeline	23
Trimming clips	26
Editing clips in the Timeline	28
Applying transitions	30
Previewing a clip or a video program	32
Adjusting audio levels	34
Panning or balancing audio	36
Applying effects	38
Using the Title window	41
Creating composites	42
Animating a still image	44
An overview of output options	46
Exporting to the Web	47

**What's New in
Premiere 6.0**

DV functionality 50
 Built-in Web export for one-step Web output 53
 Enhanced Monitor and Timeline windows 55
 Audio Mixer 58
 Improved project management 60
 Visualization tools 63
 Enhanced effect support 65
 Customizable workspace 67
 New tools and a more familiar interface 69

Working with Projects

Chapter 1

Selecting an initial workspace 73
 Starting a project 73
 Specifying project settings 74
 Comparing settings using the Settings Viewer 82
 Saving and autosaving a project 83
 Opening a project 85
 Removing unused frames from source clips 86
 Using a Premiere project on another platform 87
 Setting up Premiere's scratch disks 88
 Correcting mistakes 89
 Working with windows in Premiere 90
 Using the Project window's bin view 92
 Customizing a Project or Bin window display 94
 Naming, finding, and deleting items 97
 Printing window contents 98
 Creating a text list of project files 99
 Changing the startup window 100
 Working with palettes 100
 Using other palettes 105

Chapter 2

**Capturing and Importing
Source Clips**

Capture checklist 110
 Understanding offline and online editing 111
 Connecting the analog video source 112
 Connecting the DV video source 112
 Digitizing analog video as DV 113

Recording or replacing timecode (DV only)	114
File-size limitations	116
Preparing for analog capture	117
Preparing for DV video capture	120
Using the Movie Capture window	125
Capturing clips without device control	126
Capturing clips with device control	127
Batch-capturing video	130
Capturing stop-motion animation	139
Reading timecode from source video	142
Capturing analog audio	144
Importing digital audio	145
About D1, DV, and various pixel aspect ratios	147
Importing clips	151
Importing another project	156
Analyzing clip properties and data rate	157
Using offline files	158

Chapter 3

Editing Video

Using the Monitor window	163
Selecting an editing workspace	169
Using the Timeline window	171
Editing In and Out points	180
Using named duplicate clips and unnamed instances of clips	184
Using markers	185
Editing clips	189
Editing a video program	198
Creating a counting leader	227
Creating color bars and a 1-kHz tone	227
Creating black video	228
Previewing a video program	228

	Chapter 4	
Adding Transitions	About transitions	239
	Using the Transitions palette	239
	Creating transitions	241
	Replacing a transition	247
	Changing transition settings	248
	Chapter 5	
Mixing Audio	Understanding how Premiere processes audio	255
	Adjusting gain	256
	Adjusting audio levels in the Timeline	257
	Cross-fading clips linked to video	260
	Panning or balancing a clip	262
	Working with the Audio Mixer window	263
	Adjusting audio levels in the Audio Mixer window using automation	266
	Understanding nonlinear volume changes	268
	Panning or balancing in the Audio Mixer window using automation	269
	Using a clip's left or right stereo channel only	270
	Muting one channel of a stereo clip	270
	Swapping channels in a stereo clip	271
	Viewing audio clips	271
	Chapter 6	
Creating Titles	Creating and setting up a new title	275
	Creating text objects	279
	Creating rolling and crawling text	282
	Creating graphic objects	284
	Adding a shadow	286
	Using color, transparency, and gradients	287
	Using the color picker	290
	Arranging text and graphic objects	290
	Adding a title to a project	291

	Chapter 7	
Superimposing and Compositing	About transparency	295
	Using the Video Opacity rubberband	296
	Using keys to superimpose and create composites	298
	Superimposing two or more clips	306
	Adding a background matte	306
	Creating garbage mattes	307
	Creating split screens	308
	Chapter 8	
Animating a Clip	Animating a clip's motion	311
	Rotating, zooming, delaying, and distorting	316
	Specifying an exact time for motion	317
	Specifying alpha channel and color options	318
	Saving, loading, and deleting motion settings	319
	Chapter 9	
Applying Effects	Understanding keyframes	323
	Working with keyframes	324
	Working with effects	326
	Using After Effects effects	332
	Obsolete effects	332
	Chapter 10	
Producing Final Video	About exporting video from Premiere	337
	File types available for export	337
	Exporting to videotape	338
	About creating Internet media	343
	About creating a video file for CD-ROM playback	345
	About creating a video file for use in other software	346

Exporting a video	347
Exporting a still image	348
Exporting a sequence of still images	348
Exporting a filmstrip file for editing in Adobe Photoshop	349
Exporting a project for use in Adobe After Effects	350
Processing a batch of projects	351
About export settings	352
Choosing export settings	355
About creating motion-picture film	361
Exporting an edit decision list	362
Index	371

Introduction

Welcome to Adobe® Premiere®—software that brings the world of digital video editing to the Windows® or Macintosh desktop. Premiere also provides extensive support for video capture cards, hardware systems, and many input/output formats.

Registration

So that Adobe can continue to provide you with the highest quality software, offer technical support, and inform you about new Premiere software developments, please register your application.

When you first start the application, you're prompted to register online. You can choose to submit the form directly or fax a printed copy. You can also register by filling out and returning the warranty registration card included with your software package.

Installing Adobe Premiere

You must install Premiere from the Adobe Premiere CD onto your hard drive; you cannot run the program from the CD.

Follow the on-screen installation instructions after inserting the CD. For more detailed information, see the How_to_Install file on the CD.

Learning Premiere

Adobe provides a variety of options for you to learn Premiere, including printed guides, online Help, and tool tips. Using the Adobe Online feature, you can easily access a host of continually updated Web resources for learning Premiere, from tips and tutorials to technical support information.

Adobe Acrobat® Reader™ software, included on the Premiere CD, lets you view PDF files. Acrobat Reader or Adobe Acrobat is required to view many documents included on this CD.

Using the printed documentation

Two printed documents are included with Adobe Premiere 6.0.

Adobe Premiere 6.0 User Guide Contains information on using all Premiere commands and features. The User Guide also indicates when further information on a topic is available in online Help.

The guide assumes you have a working knowledge of your computer and its operating conventions, including how to use a mouse and standard menus and commands. It also assumes you know how to open, save, and close files. For help with any of these techniques, please see your Microsoft® Windows or Mac OS documentation.

Adobe Premiere Quick Reference Card Contains basic information about the Adobe Premiere tools and palettes, and shortcuts for using them. Shortcuts are also included in the online Help.

Using online Help

Adobe Premiere also includes complete documentation in an HTML-based help system. The Premiere help system includes all of the information in the *Adobe Premiere 6.0 User Guide* plus keyboard shortcuts, full-color illustrations, and more detailed information about some procedures.

Online Help provides three ways of locating information. Use the Contents and Index tabs to find general information, and use the Search tab to look up specific words or phrases.



For more detailed information about using online Help, click the Help on Help button next to the Content, Index, and Search tabs.

To properly view online Help topics, you need Netscape Communicator 4.0 (or later) or Microsoft Internet Explorer 4.0 (or later). You must also have Javascript active.

To start online Help:

Choose Help > Help Topics, or press F1 (Windows).

Using tool tips

With the tool tips feature, you can display the name of tools, or buttons and controls in palettes.

To identify a tool or control:

Activate the window in which the tool or control appears, position the pointer over it, and pause. A tool tip appears showing the name and keyboard shortcut (if any) for the item.

If tool tips don't appear, the preference for displaying them may be turned off.

To display tool tips:

- 1 Choose Edit > Preferences > General.
- 2 Select Show Tool Tips, and click OK.

Note: Tool tips are not available in most dialog boxes.

Using Web resources

If you have an Internet connection and a Web browser installed on your system, you can use the Adobe Online feature to access additional resources for learning Premiere located on the Adobe Systems home page on the World Wide Web. These resources are continually updated and include the following:

“How To”s and Backgrounders Provide access to procedures for performing tasks in Premiere and to detailed reference information on a variety of topics. This information provides help on everything from common processes to the complex interapplication tasks necessary to prepare projects for the Web.

Tutorials and Techniques Provide step-by-step instructions on using Premiere’s features or help on performing advanced techniques. These tutorials can help you go beyond the reference information contained in the User Guide and show you how to use Premiere with other applications.

Quick Tips Provide short, time-saving procedures to help you use Premiere more effectively. Tips can be shortcuts for using new features, or instructions on using existing features more effectively.

Troubleshooting Provides access to solutions to problems you may encounter using Premiere. Check the troubleshooting information available through Adobe Online and the Adobe Web site before you call customer support.

To access Adobe’s home page for your region:

- 1 Open Adobe’s worldwide home page at www.adobe.com.
- 2 Click the Adobe Worldwide link and choose your geographical region. Adobe’s home page is customized for 20 different geographical regions.

About Adobe Online

Adobe Online provides access to the latest tutorials, quick tips, and other Web content for Premiere and other Adobe products. Using Adobe Online, you can also download and view the current version of the Premiere Top Issues document containing the latest Premiere technical support solutions. Bookmarks are also included to take you quickly to noteworthy Adobe and Premiere-related sites.

Using Adobe Online

Adobe Online is constantly updated with new content. When you set up Adobe Online to connect to your Web browser, each time you launch Premiere, the program checks Adobe Online and downloads any new content automatically. You can also view tech support documents and new files using the Help menu.

To use Adobe Online:

1 In Premiere, choose Help > Adobe Online.

***Note:** You must have an Internet connection and an Internet browser installed. Adobe Online will launch your browser using your default Internet configuration.*

2 Do any of the following:

- Click Preferences to specify connection options. General preferences affect how Adobe Online interacts with all Adobe products installed on your system, and Application preferences affect how Adobe Online interacts with Premiere. To see an explanation of each preference option, click Setup and follow the prompts. You also can set up an automatic refresh using the Update Options.

***Note:** You can also set Adobe Online preferences by choosing Edit > Preferences > Online Settings.*

- Click any button in the Adobe Online window to open the Web page to which the button is linked.
- Click the bookmark button() to view Adobe-suggested Web sites related to Premiere and Adobe. These bookmarks are automatically updated as new Web sites become available.
- Click Close to return to Premiere.

Accessing Adobe Online through the Help menu

The Help menu includes options to view and download information from Adobe's Web site.

To view updated articles or documents:

Click Help and choose the topic you want to view.

Other learning resources

Other learning resources are available but are not included with your application.

Classroom in a Book The official training series for Adobe graphics and publishing software. This book is developed by experts at Adobe and published by Adobe Press. The *Adobe Premiere Classroom in a Book* includes lessons about using Premiere. For information on purchasing *Adobe Premiere Classroom in a Book*, visit the Adobe Web site at www.adobe.com, or contact your local book distributor.

The Adobe Certification program Offers users, instructors, and training centers the opportunity to demonstrate their product proficiency and promote their software skills as Adobe Certified Experts, Adobe Certified Instructors, or Adobe Authorized Learning Providers. Certification is available for several different geographical regions. Visit the Partnering with Adobe Web site at www.partners.adobe.com to learn how you can become certified.

See www.adobe.com/premiere for updated information on additional learning resources.

Customer support

When you register your product, you may be entitled to technical support for up to 90 days from the date of your first call. Terms may vary depending on the country of residence. For more information, refer to the technical support card provided with the Premiere documentation.

Customer support on Adobe Online


Adobe Online provides access to FAQs (Frequently Asked Questions) and troubleshooting information that provides solutions to common problems.

Additional customer support resources

Adobe Systems provides several forms of automated technical support:

- See the ReadMe and ReadMe First! files installed with the program for information that became available after this guide went to press.
- Explore the extensive customer support information on Adobe's World Wide Web site (www.adobe.com). To access Adobe's Web site from Premiere, choose Help > Adobe Online or click the icon at the top of the toolbox. See "Using Web resources" on page 3.
- Read the Top Issues PDF that is available from the Help menu.

An Overview of Adobe Premiere



With Adobe Premiere 6.0, you can capture, import, assemble, and edit video, audio, and still images. Premiere provides highly intuitive windows and palettes, allowing you to master every creative aspect in the development of your video project. New export modules provide an exceptional variety of options for exporting to the Web, as well as the option to export to tape, CD-ROM, or videotape.

This interactive overview of Adobe Premiere contains a number of brief lesson modules designed to provide introductions to key features of the program. You can complete the lesson modules in ordered sequence, or choose individual modules to tailor your introduction to specific topics. Once you learn the basics of using the program, you'll be ready to explore the extensive editing, compositing, and exporting features of Premiere. If you need video clips to practice with while stepping through this overview, use the included sample clips, which are located in the Sample folder on the Premiere CD.

Starting Premiere

Setting up your workspace

The workspace is the arrangement of windows, window features, and palettes in Premiere. Premiere includes four prearranged workspace options: A/B Editing, Single-Track Editing, Effects, and Audio. You can also customize the workspace to suit your editing style and save it as a file for use in other projects.

Choosing a workspace When you start Adobe Premiere for the first time, the Select Initial Workspace dialog box appears, in which you choose your initial workspace: *A/B Editing*, which uses a simple A/B roll environment and is recommended for those who are new to video editing, or *Single-Track Editing*, which uses a professional editing environment in which the Video 1 A and B tracks are collapsed into one track. Single-Track Editing is recommended for those who have experience working with video-editing software. If you are unsure of which option to select, select A/B Editing.

The initial workspace dialog box only appears the first time you start the application. If you want to change the workspace at any other time, choose Window > Workspace. Adobe recommends you do not switch between A/B Editing and Single-Track Editing after you've begun editing a project, as this may cause unpredictable behavior. However, you can use A/B Editing for one project and Single-Track Editing for another, or switch back and forth if you have not yet begun working with the clips in your project.

Premiere also includes an *Audio* workspace and an *Effects* workspace that display the windows and palettes most often used when performing audio or effect edits. You can switch to the Audio or Effects workspace at any time during your editing process. You can also change individual components of the windows and palettes to create your own custom workspace. For more information, see “Selecting an editing workspace” on page 169.

- To select a new workspace, choose Window > Workspace, and then select a workspace option.
- To save changes you've made to the workspace, choose Window > Workspace > Save Workspace. Once you save a workspace, it appears as an option in the Workspace menu and you can choose it from within any project.

Looking at the A/B Editing workspace If you plan to perform only simple cuts and edits, and prefer to work with a separate transition track, you may want to use the A/B Editing workspace. This workspace displays Premiere's windows in their most basic format, so that they are easy to understand and use (it most resembles Premiere 4.2). The primary workflow for A/B editing is dragging clips from the Project window to the Timeline window, and from there trimming, editing, and rearranging clips. When you use the A/B Editing workspace, clips open in individual Clip windows, the Monitor window is in Single View, and the Timeline displays three separate Video 1 tracks: Video 1A, Transition track, and Video 1B track.



In the A/B Editing workspace, you drag clips from the Project window to the Timeline window.

Looking at the Single-Track Editing workspace Most professional video editors use a single-track editing system for precise placement of clips in the Timeline. In this workspace, video clips and transitions are on the same track—though you can expand the track to display a transition track between two Video 1 tracks. However, the two Video 1 tracks are synchronized and behave as one track. The primary workflow used in the Single-Track Editing workspace is dragging clips from the Project window to the Source view of the Monitor window, setting In and Out points, and inserting or overlaying the clip in the Timeline at a precise location.



In the Single-Track Editing workspace, you drag clips to the Source view of the Monitor window (left), where you edit them before placing them in the Timeline window (right).


Starting a project

After you start Premiere and select your initial workspace, the Load Project Settings dialog box opens. Here you can choose a preset group of project settings for a particular editing environment such as DV, QuickTime, or Video for Windows. If you prefer to choose your settings individually, select the preset that most closely matches your editing environment, and then click Custom and choose specific settings in the Project Settings dialog box. If you want to open an existing project, click Open.

Create a new project or open an existing one You can start a new project by simply starting Premiere and choosing a project preset from the Load Project Settings dialog box. If you want to start a new project after Premiere is already open, choose File > New Project. The Load Project Settings dialog box opens.

(To change the window that opens at startup, see “Changing the startup window” on page 100.)

Determine your project settings The best way to ensure that Premiere handles your video clips correctly is to use the preset included with your capture card software or the appropriate preset included with Premiere. If none of the available presets meet your needs, choose project settings that are identical or at least compatible with your capture settings (see your capture card or DV camcorder documentation) and your clip settings. For example, if you capture DV video at 720 x 480 frame size, use that same frame size for your project. For a complete description of project settings, see “Specifying project settings” on page 74.




If your capture card manufacturer did not provide presets, or if you are not using their presets for a specific project, keep the following in mind when choosing project settings:

- If you don't see a preset that matches your video, select the closest match, and then click Custom and choose the settings from the New Project Settings dialog box. Once you have selected all the appropriate custom settings, click Save to create a preset for use in other projects.
- You can open the Project Settings dialog box at any time by choosing Project > Project Settings. However, making changes to settings once you have begun editing is not recommended, as it may cause unwelcome changes to the clips in the project.
- Be sure to review and compare all of the settings in your project using the Settings Viewer: choose Project > Settings Viewer. In most cases, it is important that the capture, project, and individual clip settings are the same in any given project. Discrepancies between these settings can cause unexpected behavior in your previews and final output. By default, your export settings match your project settings. However, they do not have to match any other project settings, so you can change them if you want without affecting the project. For more information, see “Comparing settings using the Settings Viewer” on page 82.

Getting to know the work area

Work area overview

Once you open a project, the Premiere work area appears. If you've worked with other Adobe applications, the Premiere work area will look familiar, with the command menus at the top of the screen, windows to perform your assembling and editing, the toolbox, and the floating palettes.




Premiere's Single-Track Editing workspace: A. Project window B. Monitor window (Source view on the left and Program view on the right) C. Timeline window D. floating palettes

Using tools and palettes

The Premiere toolbox contains tools for selecting, editing, and viewing your clips. The Adobe floating palettes contain additional features that help you monitor, modify, and enhance your work. You can hide and rearrange the palettes to organize your work area as needed. For more information on palettes, see “Working with palettes” on page 100. For more information on tools, see individual tool names in the index.

Select a tool The toolbox is located at the top left of the Timeline window. Some tools in the toolbox have pop-out panels (represented by a small triangle on the right side of the panel) that contain additional hidden tools.

- To select a tool, click its icon in the toolbox.
- To select a hidden tool, click the current tool in the toolbox and select the tool you want from the pop-out panel.




Selecting a hidden tool

Display the palettes When you first start Adobe Premiere, floating palettes appear stacked in default groups. Use the following techniques to show and hide palettes:

- To bring a palette to the front of its group, click the palette’s tab.
- To show or hide a palette as you work, choose the appropriate Window > Show or Window > Hide command.
- To minimize or expand a palette in Windows, click the left-most button at the top right of the palette group.
- To minimize or expand a palette in Mac OS, click the small square at the top right of the palette group.
- To hide or display all open palettes, press Tab.

Arrange the palettes Depending on your available screen area and work preferences, you may want to reposition and regroup the palettes into more efficient arrangements.


- To move an entire palette group, drag the group's title bar.
- To rearrange or separate a palette group, drag a palette's tab. You can drag a palette to another group or to its own separate group. Palette positions are saved with the workspace.



Drag a palette tab to separate the palette from the group.

Display a palette or window menu Most palettes and windows have pop-out menus containing commands and options that add to their functionality.

- To display a palette or window menu, position the pointer over the black triangle at the top right of the palette or window, and hold down the mouse.



Displaying a palette menu

Looking at the Project window

All of the clips you import into your project—video, still image, sequence, and audio—are listed in the Project window. Every project has only one Project window; if you close this window, you close the project. The Project window is customizable, so you can sort and view your clips using the options most appropriate for your editing style. For more information on the Project window, see “Using the Project window’s bin view” on page 92 and “Customizing a Project or Bin window display” on page 94.

View clips in the Project window You can view and add information for every clip in your project. When you select a clip in the Project window, the thumbnail viewer displaying the *poster frame* (the frame used for icon view and as a sample frame for titles), along with the clip name, media type, video information, duration, and data rate, appears in the top left corner of the window. If the clip is a video, click the Play button (▶) to preview it in this window.

You can expand the size of the Project window to view and enter clip information for every clip in the window.


- To expand the window, drag any corner (Windows) or the lower right corner (Mac OS).

Organize clips By default, Premiere uses the List view (≡) and displays clips alphabetically by name.

- To sort clips by a heading, click the heading. For example, if you've captured a series of clips from tape and want to list them in order by timecode, click the Timecode heading.
- To reverse the order of clips under a heading, click the heading again.
- To arrange clips freely in the Project window, use the Icon view (☐) and drag the clip icons into the positions you want.

Bins, which resemble folders, are located in the left panel of the Project window; use them to organize your clips into groups. When you import clips, they are added to the currently selected bin. You can reuse bins in multiple projects by saving and exporting a bin as a separate file.

- To view the contents of a bin, click the bin name—the contents appear on the right side of the Project window.
- To save and export a bin as a file, select the bin and choose Project > Export Bin from Project.
- To import a saved bin, choose File > Import > File, locate and select the bin file, and choose Open.




A. Thumbnail viewer and poster frame B. Bins C. Clip
D. Clip information E. Search F. New Bin G. Create
Item H. Delete Selected Item I. Resize Bin Area J. Icon
view K. Thumbnail view L. List view

Looking at the Timeline window

Once you've captured or imported clips into your project, use the Timeline window to organize your clips sequentially, make changes to a clip's duration and location, add transitions, superimpose clips, and apply effects, opacity, and motion. Once you've completed all your editing, export the Timeline contents to any variety of file formats or directly to videotape.


Explore the Timeline window Premiere's Timeline window provides an overview of all the clips in your video program, as well as their durations, locations, effects, opacity, fades, waveforms, and other features. You can add transitions between clips on the Video 1 track, and superimpose clips that are on the Video 2 or higher tracks.



Timeline window in the Single-Track Editing workspace: A. Work area bar B. Edit line C. Tools D. Superimpose track E. Adjustable track header border F. Keyframe and Opacity icons G. Shy Video track icon H. Video track I. Audio track J. Waveform, Keyframe, Volume, and Pan icons K. Lock track icon L. Shy Audio track icon M. Time Zoom Level N. Timeline window menu button O. Track Options Dialog button P. Toggle Snap to Edges button Q. Toggle Edge Viewing button R. Toggle Shift Tracks Options button S. Toggle Sync Mode button

Expand the tracks You can expand each track in the Timeline to display more controls.

- Click the triangle next to the Video 2 track name; then click the Keyframe (◆) icon to set and view effect keyframes, and click the red Display Opacity Rubberbands (■) icon to set and view handles on the Opacity rubberband. (The Video 1 track does not include an Opacity rubberband; clicking the triangle next to the Video 1 track name displays the keyframe area only.)
- Click the triangle next to the Audio track name; then click the Keyframe (◆) icon to set and view effect keyframes, click the red Display Volume Rubberbands (■) icon to set and view handles on the Volume rubberband, click the blue Display Pan Rubberbands (■) icon to set and view handles on the Pan rubberband, and click the Waveform (⚡) icon to view the audio clip's waveform. See “Adjusting audio levels” on page 34 and “Panning or balancing audio” on page 36 for information on using the audio track rubberbands.
- Click the Time Zoom Level menu at the bottom left corner of the window to select a new frame range to view. Select a shorter duration (such as 4 Frames) to zoom into the project, or a longer duration (such as 20 Seconds) to see more of the project in the window. To fit the entire Timeline contents in the viewable area, press the backslash key (\) on your keyboard.



Choosing a value from the Time Zoom Level menu expands or compresses your view of the footage in the Timeline.

Looking at the Monitor window

Use the Monitor window to view individual clips, preview the Timeline, set In and Out points, set markers, add and remove clips from the Timeline, and trim clips. When you use the Single-Track Editing workspace, the Monitor window includes the Source view (left side of window) and the Program view (right side of window). When you use the A/B Editing workspace, the Monitor window displays only the Program view and uses individual Clip windows instead of the Source view (you can change this default at any time by choosing a new Monitor window view). The Source view (or Clip window) displays a single clip as it appears on your hard disk (project settings do not affect playback from this view). Use the Source view (or Clip window) to prepare a clip for inclusion in the Timeline or to edit a clip you've opened from the Timeline. The Program view displays the current state of the Timeline—when you preview the Timeline, it plays in the Program view.

Switch among Monitor window views You can display the Monitor window in any of three different modes to suit your needs and work style:

-  Dual View mode displays both the Source and Program views. Video editors experienced in using high-end video editing systems may be able to edit faster and more precisely using both the Source and Program view controllers. This is the default window display for the Single-Track Editing workspace.



Monitor window in Dual View

-  Single View mode displays only the Program view. Individual clips open in individual Clip windows. If you're learning how to edit video, you may find it faster and easier to work in Single View mode. This is the default window display for the A/B Editing workspace.



Monitor window in Single View


- (🔍) Trim mode is a “zoomed-in” view of a particular edit on the Timeline. When you select Trim mode, the edit line automatically jumps to the next edit in the Timeline, and the clips at that edit point appear in the Monitor window. Use the controls in the Trim window to adjust the In and Out points of those clips. For more information on trimming using Trim mode, see “Using the Trim view” on page 219.



Monitor window in Trim View

To change views, click the view buttons (🖼️ 📺 🔍) at the top of the Monitor window or choose a mode from the Monitor window menu.


Look at the playback controls The playback controls are the same for all windows. You can access these controls from a Clip window, or the Source view or Program view of the Monitor window.



Preview controls: A. Frame Back B. Frame Forward
C. Stop D. Play E. Loop F. Play In to Out

Look at the Source view controller The Source view controller (lower left side of the Monitor window) appears only when the Monitor window is in Dual View mode. To use this controller, drag a clip from the Project window to the Source view window, and then use the controller to preview, set In and Out points, add markers, specify whether to take audio or video, and insert or overlay a clip onto the target track in the Timeline.

Individual Clip windows contain the same controllers as the Source view. However, if you want to perform L-cuts, J-cuts, or six-point edits, you must use the Source view in the Monitor window. For more information, see “Editing In and Out points” on page 180.



A. Frame Back B. Frame Forward C. Stop D. Play
E. Loop F. Play In to Out G. Insert H. Overlay

Look at the Program view controller Use the controller under the Program view (lower right side of the Monitor window) to remove clips or portions of clips from the Timeline, add transitions, set Timeline markers, and preview the Timeline.

The Marker menu and the Mark In and Out controls apply to the entire Timeline. All other Program view controls affect only the clips in the *Target tracks*. Target tracks indicate which Timeline video or audio track is set to receive the video or audio from the Source view (or Clip window) or be affected by the Lift, Extract, Insert, or Overlay command.



A. Target video track B. Target audio track C. Marker menu
D. Mark In E. Mark Out F. Lift G. Extract H. Previous Edit
I. Next Edit J. Add Default Transition

Assembling and editing video

Acquiring source material

The video, audio, and still image clips you use in your project can come from a variety of sources. You can capture DV video and audio directly from a DV camcorder using IEEE 1394 (FireWire/i.Link) or capture analog video and audio using a supported video capture card (see <http://www.adobe.com/premiere> for a list of supported cards). You can import stills from other applications such as Adobe Photoshop and Adobe Illustrator, import audio that you've transferred to your hard disk from a CD, or import a folder containing a variety of files in different formats.

Import one or more clips Premiere supports a variety of file formats, including .MOV, .AVI, .AIF, .TIF, .JPEG, .BMP, and .PSD. For more information, see “Importing clips” on page 151.

- To import a clip, choose File > Import File, locate and select a clip, and then click Open.
- To import multiple clips in Windows, choose File > Import File, locate the clips and press Control as you select multiple individual clips or press Shift and select a range of clips, and then click Open.
- To import multiple clips in Mac OS, choose File > Import File, locate the clips and press Shift as you select each clip, and then click Open.

When you create still images for use in Premiere, always create them at the same aspect ratio as the other files in your project; otherwise, they may distort when you preview or output the project (see “About D1, DV, and various pixel aspect ratios” on page 147). If a file contains an alpha channel, you can use the alpha channel to create transparency in Premiere. For more information on using alpha channels, see “Using the Alpha Channel key” on page 302 and “Specifying alpha channel and color options” on page 318.


Import a folder of mixed media You can import folders containing any variety of video, audio, and still clips.

- To import a folder into a project, choose File > Import > Folder, locate and select a folder, and then click OK.




Capture video Premiere supports the direct capture of DV and analog video. For detailed information on capturing from Premiere, see Chapter 2, “Capturing and Importing Source Clips.” To capture DV audio and video, do the following:

- 1 Plug one end of your IEEE 1394 (FireWire/i.Link) cable into the Video Out port of your DV camcorder or deck, and then plug the other end into the IEEE 1394 (FireWire/i.Link) port on your computer.
- 2 Open Premiere and select the appropriate preset from the Load Project Settings dialog box. Use the preset included with your camera or capture card software, or one of Premiere’s DV presets. Click OK.
- 3 If your camcorder or deck supports device control, choose Edit > Preferences > Scratch Disks/Device Control (or click Edit in the Capture window). Select a device from the Device menu, click Options, and select the options that match your DV device (camcorder or deck). See your DV device documentation for more information. Click OK.



- 4 Choose File > Capture > Movie Capture. When using device control, use the controls in the Movie Capture window to play and record the video. When not using device control, use the controls on your device to play the video and use the controls in the Movie Capture window to record the video. Captured clips are automatically added to the open Project window.



A. Preview window B. Slow Play C. Reverse Slow Play
 D. Play E. Stop F. Frame Forward G. Frame Forward
 H. Take Video I. Take Audio J. Shuttle Slider K. Rewind
 L. Fast Forward M. Pause N. Record O. Set In P. Set Out


Adding clips to the Timeline

The Timeline is where you create and edit your video program. After you capture or import your clips, the next step is adding them to and arranging them in the Timeline. You can add clips to the Timeline using several different methods.

Methods for adding clips Choose the method that works best with your editing style. You can use any of the following methods for assembling footage, regardless of whether your workspace is set up for A/B or Single-Track Editing:

- Drag clips from the Project window, Source view, or Clip window to the Timeline.
- Arrange clips in a Project window bin or a Storyboard window and then transfer them to the Timeline using the Automate to Timeline command.
- Drag a clip from the Project window to the Source window (or double-click it in the Project window to open it in a Clip window), set In and Out points, and then use the Insert or Overlay options to add the clip to the selected target track on the Timeline.

Dragging clips to the Timeline When you want to assemble a series of clips quickly with little or no trimming (usually called a rough cut), drag clips from the Project window directly to the Timeline.





Drag clips directly from the Project window to the Timeline.

Use the Automate to Timeline command When you want to experiment with the layout of your clips before final placement on the Timeline, use the Icon view in the Project window or create a storyboard to visually organize them; then transfer them automatically to the Timeline. You can save a bin or a storyboard and open it in other projects. For more information, see “Organizing clips using bins” on page 93 or “Creating a storyboard” on page 203. To create a storyboard, do the following:

- 1 Choose File > New > Storyboard.
- 2 Drag clips from the Project window to the Storyboard window in the order in which you want them aligned in the Timeline. Notice the arrows that appear between the clips to show the arrangement.
- 3 Rearrange the clips by dragging them to new locations.
- 4 If you want, double-click any clip and set new In and Out points or markers. Premiere automatically updates clips in the storyboard to reflect any changes.

To automatically transfer contents of a bin or storyboard to the Timeline, do the following:

- 5 Choose Project > Automate to Timeline.
- 6 In the Automate to Timeline dialog box, select the placement options and click OK. Premiere automatically transfers the clips to the Timeline. For more information, see “Adding multiple clips using an automated process” on page 201.



Choose Automate to Timeline to transfer your bin or storyboard (shown) clips, in order, to the Timeline window.

Insert/Overlay from the Monitor window Source view Use the Source view (or the Clip window) to set In and Out points for your video clips and then insert or overlay them on the Timeline:

- 1 Drag a clip from the Project window to the Source view. If you're using A/B Editing, double-click a clip in the Project window to open it in a Clip window.
- 2 Click the Play button (▶) under the Source view (or Clip window) to preview the clip. As you preview, determine which portions you want to use and which you don't.
- 3 In the Jog Tread, drag the Mark In (⏪) point to the frame you want to set as the first frame for your clip. If your clip contains both audio and video, you can set different In and Out points for each by pressing Alt (Windows) or Option (Mac OS) as you drag the In or Out point.



- 4 Drag the Mark Out (⏩) point to the frame you want to set as the last frame for your clip.

- 5 To add the trimmed clip to the Timeline, either drag it from the Source view (or Clip window) to the Timeline, or use the Insert () or Overlay () buttons. For more information, see “Adding a clip to the Timeline” on page 198.





In the Single-Track Editing workspace, you drag clips into the Source view of the Monitor window, where you edit them before placing them in the Timeline window.

Trimming clips

Video clips often contain more footage than you need or want to use in your video program. To create scenes, cuts, and transitions, you'll need to trim your clips, removing the parts that you don't need. Trimming clips is an essential part of creating a video program, something you'll do many times. Premiere provides a number of different ways to trim clips, including quick rough-cut tools and more precise frame-by-frame views. You can trim clips in the Source view (or Clip window) before you add them to the Timeline, as described in "Adding clips to the Timeline" on page 23, or you can trim them directly in the Timeline window.

Trimming In and Out points in the Timeline You can easily remove unwanted portions of your video or audio clips in the Timeline using the selection tool (⌘). To determine where you want to make an edit, preview the Timeline clip in the Program view. To trim In and Out points, do the following:

- 1 Watch the Program view as you drag the edit line in the time ruler of the Timeline. Stop when you see the frame that you want to set as the clip's new In point.
- 2 In the Timeline, position the selection tool at the left end of the clip. The cursor turns into a trim tool, which is a double-sided arrow with a red bracket (⌘). The direction of the bracket, open left (⌘) or open right (⌘), indicates which clip the tool will modify.
- 3 To edit the In point, drag to the right until the cursor snaps to the edit line (make sure that Snap to Edges (⌘) is on).
- 4 Using the Program view to preview, drag the edit line in the time ruler of the Timeline again until you see the frame you want to set as the clip's new Out point.
- 5 Position the selection tool at the right end of the clip; when it turns into the trim tool, drag to the left until it snaps to the edit line.




Using the selection tool, drag the edge of a clip (left) to get a new In or Out point (right).

Editing clips in the Timeline

Once you've assembled clips in the Timeline, you may want to make adjustments to a clip's location or the In point of one clip in relation to the Out point of the next. Premiere includes several tools to help you do this.

Perform a ripple edit A ripple edit trims the specified clip but keeps the duration of all other clips the same. The trim, however, ripples through the project: other clips are pulled or pushed depending on whether you shorten or lengthen the clip. Therefore, the duration of the entire video program changes.




A. Before performing a ripple edit B. Performing a ripple edit C. Result of a ripple edit

To perform a ripple edit, do the following:

- 1 Select the ripple edit tool () from the toolbox.
- 2 Position the cursor between the clip you want to trim and the adjacent clip. The cursor becomes a double-sided arrow with a red bracket. The direction of the bracket (open left  or open right ) indicates which clip the tool will modify.

- 3 Drag the ripple edit tool to trim the clip; then release the mouse button.



Using the ripple edit tool, drag the edge of a clip (left). The edit ripples through the Timeline (right).

Perform a rolling edit A rolling edit trims the specified clip and the adjacent clip but keeps the duration of all other clips and the project the same. When you use the rolling edit tool to subtract frames from a clip, the adjacent clip must contain additional frames that can be added to fill the gap.



A. Before performing a rolling edit B. Performing a rolling edit C. Result of a rolling edit

To perform a rolling edit, do the following:

- 1 Select the rolling edit tool (⇄) from the toolbox.
- 2 Position the cursor between the clip you want to trim and the adjacent clip. The cursor becomes two double-sided arrows. The tool modifies both clips.
- 3 Drag the rolling edit tool to trim the clip; then release the mouse button.



Using the rolling edit tool, drag the edge of a clip (left). The edit affects only the adjacent clip (right).


Applying transitions

Use transitions between clips in your video program to create a visually pleasing, creative transition from one clip to the next. Premiere provides a variety of transitions, including blends, wipes, and doors. Other transitions, such as QuickTime transitions, are also available.

Add a transition in the A/B Editing workspace Transitions overlap the ends of two clips on the Video 1 track. The A/B Editing workspace displays the Video 1 track expanded into three separate tracks so you can visually determine the amount of overlap to use with the transition. For information on applying transitions in the Single-Track Editing workspace, see “Working in the Single-Track Editing workspace” on page 243. To add a transition, do the following:

- 1 In the Timeline, position one clip in the Video 1A track and another in the Video 1B track, making sure to overlap them by at least a few frames.

- 2 If necessary, choose Window > Show Transitions. Premiere stores all of its transitions in the Transitions palette, sorted in folders by type. You can arrange them any way you want or even create new folders for your favorite transitions to enhance your workflow.
- 3 In the Transitions palette, click the triangle next to a folder name and locate the transition you want.
- 4 Drag the transition's icon from the Transitions palette to the Transition track, at the point where the two clips overlap. Premiere automatically expands the transition to fill the overlap.



Drag a transition to the transition track (left). The transition fills the overlapping space (right).

Apply a default transition If you frequently use one transition in a project, you can set it as the default transition and apply it using a Monitor window control. Premiere automatically uses Cross Dissolve as the default transition. You can use the default transition in any workspace. To add a default transition when using the A/B workspace, do the following:

- 1 Position two clips in the Video 1 track in the Timeline so that they meet.
- 2 In the Timeline, press Ctrl+Alt+Shift (Windows) or Command+Option+Shift (Mac OS) and click in the overlap between the two clips.
- 3 To change the default transition, select a transition in the Transitions palette, and then choose Set Selected as Default from the Transitions palette menu. For more information on default transitions, see “Specifying and adding a default transition” on page 246.

Previewing a clip or a video program

Premiere provides a number of playback and preview options to choose from, depending on what you want to view and at what quality. Using different options, you can play or preview individual clips or the entire contents of the Timeline.


Play a single clip To play back a single clip, do any of the following:

- Select a clip in the Project window and click the Play button (▶) under the thumbnail viewer that appears at the top of the window.
- Double-click a clip in the Project window and click the Play button (▶) in the Clip window controller.
- Drag a clip from the Project window to the Source view of the Monitor window, and then click the Play button (▶) in the controller under the Source view.

Play the video program Play back the contents of the Timeline in the Program view of the Monitor window. If you are using the DV editing mode, or if your analog capture card supports it, you can play your program on your DV device or connected television monitor. For more information, see “Previewing on another monitor” on page 232.

You can play your video program using any of the following techniques:

- To play back the program without effects, click the Play button (▶) under the Program view, or select the Timeline and press the spacebar. To stop the playback, click the Stop button (■) in the Program view or press the spacebar again.



Drag the yellow work area bar over the area you want to preview.

- To play back the program with effects, drag the yellow work area bar over the portion of the program you want to preview, and then press Enter (Windows) or Return (Mac OS). If prompted, name and save the project. Premiere builds (renders) a preview file of the selected area, and then plays it in the Program view.
- To *render-scrub* (manually scrub through the program viewing effects), press Alt (Windows) or Option (Mac OS) as you drag the edit line in the Timeline's time ruler.
- To manually scrub through the program *without* viewing any effects, drag the edit line in the Timeline's time ruler or drag the shuttle slider under the Program view.


Mixing audio

Adjusting audio levels

You can adjust the level (also called gain or volume) of an audio clip at precise locations in your video program using either the Volume rubberbands in the Timeline or the volume faders in the Audio Mixer.

Adjusting volume in the Timeline Under each audio clip in the Timeline is a Volume rubberband on which you can create and adjust handles to adjust the volume in an audio clip.

- To see the Volume rubberband in the Timeline, click the triangle to the left of the audio track name, and then click the red Display Volume Rubberbands (▣) icon.
- To add volume handles, click anywhere along the Volume rubberband. Premiere includes a default handle at the beginning and end of every clip. To fade volume in from the beginning of a clip, click to create a handle where you want the audio to fade in, and then drag the first default handle (located at the beginning of the clip) down to the bottom of the track. The clip's volume will fade in from the first to the second handle. For more information, see “Adjusting audio levels in the Timeline” on page 257.




Click the Volume rubberband to create handles (left), and then drag the handles up or down to fade the volume in or out (right).

Adjusting volume with the Audio Mixer Using Audio Mixer controls, you can adjust and record the volume levels for each audio track in your video program in real time, all while listening to and watching the video program. For more information, see “Adjusting audio levels in the Audio Mixer window using automation” on page 266. To adjust gain, do the following:

- 1 In the Timeline, position the edit line where you want to start adjusting the volume.

- Do one of the following:
 - Choose Window > Workspace > Audio to change your workspace to one optimized for editing Audio.
 - Choose Window > Audio Mixer to leave your workspace as is and just display the Audio Mixer window.
- In the Audio Mixer, click the Automation Write () button above the track you want to edit. When Automation Write is activated, Premiere records all of your settings. For more information on automation, see “Working with the Audio Mixer window” on page 263.
- To gang tracks together so that when you move one volume fader () , the other tracks’ faders keep their relative relationship, right-click (Windows) or Control-click (Mac OS) the volume fader and choose a gang option. For example, right-click the Volume Fader for track 1 and choose Gang 1 from the menu that appears; then right-click the volume fader for track 2 and choose Gang 1 from the menu to gang together the volume faders for tracks 1 and 2.
- Press the spacebar to play the audio and then drag the volume fader () up to increase volume or down to decrease volume.
- When you’re done, expand the audio track in the Timeline, click the red Display Volume Rubberbands () icon, and see how Premiere automatically added handles to the Volume rubberband.




When you choose Automation Write, changes you make in the Audio Mixer (left) appear in the corresponding audio track in the Timeline (right).

Panning or balancing audio

Panning an audio clip shifts the sound from a single (monophonic) channel to either the left or right stereo channel; balancing adjusts the balance of sound between both channels in a stereo clip. In Premiere, you can use the pan controls to pan or balance audio in the Timeline or the Audio Mixer. To use pan controls, your project must use stereo audio settings. To determine your project's audio settings, choose Project > Project Settings > Audio and look at the Format setting.

Panning or balancing audio in the Timeline In addition to the Volume rubberband, Premiere includes a Pan rubberband under each audio clip in the Timeline. You can create handles to pan or balance your audio clips using this rubberband. For more information, see “Panning or balancing clips in the Timeline” on page 262. To pan audio, do the following:

- 1 If necessary, click the triangle to the left of the audio track name to expand the track, and then click the blue Display Pan Rubberbands icon (☐).
- 2 Click the Pan rubberband to add handles. Then drag a handle up to shift volume to the left channel or drag down to shift volume to the right channel.




A. Panning audio to the left channel B. Panning audio to the right channel

Panning or balancing audio in the Audio Mixer Use the Pan control in the Audio Mixer to precisely position audio in a stereo channel. For more information, see “Panning or balancing in the Audio Mixer window using automation” on page 269.

- 1 In the Timeline, position the edit line where you want to begin editing.
- 2 Do one of the following:
 - Choose Window > Workspace > Audio to change your workspace to one optimized for editing Audio.
 - Choose Window > Audio Mixer to leave your workspace as is and just display the Audio Mixer window.

- 3 Click the Automation Write (\mathcal{A}) button above the track you want to pan. When Automation Write is activated, Premiere records all of your adjustments. For more information on automation, see “Working with the Audio Mixer window” on page 263.
- 4 Press the spacebar to play the audio and then drag the Pan control (\odot) to the left or right. As you drag, handles are added to the Pan rubberband in the Timeline.




Adjustments you make to the Pan control in the Audio Mixer (left) appear in the corresponding audio track in the Timeline (right).

Using effects, transparency, and motion

Applying effects


Premiere includes numerous audio and video effects—with many new video effects from Adobe After Effects! Apply an effect by dragging it from the Video or Audio effect palette to a clip in the Timeline. Once applied, all effects are stored in the Effect Controls palette, where you can access effect settings, turn effects on or off, enable keyframes, or delete effects.



Apply an effect Using palettes, it is easy to apply and control both video and audio effects in Premiere. For more information, see “Working with effects” on page 326. To apply an effect, do the following:

- 1 To set your workspace to one optimized for editing effects, choose Window > Workspace > Effects.
- 2 To see the effects available in Premiere, click the Video or Audio tab in the effects palette group. Then click the triangle next to a folder name to view the effects in that folder.
- 3 To apply an effect to a clip, drag it from the palette to a clip in the Timeline. A blue line appears across the top of the clip, indicating that the effect has been applied.


- If the effect has adjustable settings, adjust them in a Settings dialog box or the Effect Controls palette.



To apply an effect, drag it from the Video palette to a clip in the Timeline (left). A blue line appears at the top of the clip (right).

Use keyframes to animate an effect When you apply an effect with adjustable settings, you can animate the effect by changing its settings over time using keyframes. A keyframe contains information about the following:

- Which effect is changing
- The point in time when the change occurs
- The settings for the effect at the keyframe's point in time




For more information on keyframes, see “Understanding keyframes” on page 323.

Set effect keyframes You can use keyframes only with effects that have adjustable settings.

- In the Timeline window, click the triangle (▾) next to the track name to expand the track containing the clip with the effect.
- Click the keyframe icon (◊) to display the keyframe line.
- If a clip has more than one effect applied, click the triangle next to the effect name (under the clip's name in the Timeline) and select the effect from the menu that appears, or select the effect in the Effect Controls palette.

- 4 Position the edit line at the point where you want to create a keyframe and do one of the following:
 - Click the Keyframe Navigator's Add/Delete Keyframe box (□) to set a new keyframe and then, if you want, adjust the settings in the Effect Controls palette or click Setup in the Effect Controls palette and adjust the settings in the dialog box that appears.
 - Adjust the settings in the Effect Controls palette or click Setup in the Effect Controls palette and adjust the settings in the dialog box that appears. Premiere automatically adds a keyframe at that location.




Click Setup (left) to view the Settings dialog box for an effect (right).

- 5 To select an existing keyframe, click the Keyframe Navigator's Previous Keyframe (◀) arrow or Next Keyframe (▶) arrow.

Use the Effect Controls palette to manage effects

Once you've applied an effect to a clip, use the Effect Controls palette to adjust settings, hide the effect during previews, or delete the effect. For more information, see "Applying and controlling effects" on page 327.

- If necessary, choose Window > Show Effect Controls.
- To see all of a clip's effects, select the clip in the Timeline. Video or audio effects appear in the Effect Controls palette in the order they were applied.




- To adjust an effect's settings when no keyframes are set, adjust the controls under the effect name in the Effect Controls palettes, or click Setup and adjust the settings in the Settings dialog box.
- To adjust an effect's settings when keyframes are present or when you want to set a keyframe, first position the edit line over the clip; then adjust the controls under the effect name in the Effect Controls palettes, or click Setup and adjust the settings in the Settings dialog box.
- To temporarily turn an effect on or off, click the Effect Enabled button (f).
- To remove all keyframes from an applied effect, click the Keyframing Enabled button (Ⓢ). A stopwatch icon appears in this button only when a keyframe has been added to the effect.

Using the Title window


Use the Title window to create titles, rolling credits, symbols, or simple drawings. When you save a title, Premiere automatically adds it to the open Project window and applies the appropriate transparency key for easy superimpositions. For detailed information on creating titles, see Chapter 6, "Creating Titles."

Creating a title When you use Premiere's Title window, you can type text and draw images directly in the window.

- 1 Choose File > New > Title.
- 2 In the Title window, select the type tool and then click to make an insertion point.



- 3 Type your text, and then close the window. Click Yes to save the file, type a filename, and click Save. Once you save the title, Premiere automatically adds the title file to your Project window.




Creating composites

Premiere makes it easy to create composites, also known as superimpositions. Using different types of transparency keys such as alpha channels or blue screens, you can superimpose two or more clips on top of one another and create composites containing selected portions of each clip. Superimposing is commonly used to add titles and credits to a movie, to add a logo to an advertisement, and to change the background behind a person or figure in a video clip.

Preparing for transparency If you plan to use transparency in your video program, take the time to prepare your footage for transparency effects. For example, shoot your video in front of a solid-colored screen that contrasts with the subject you are taping, or save still images with an alpha channel. For more information, see “About transparency” on page 295. (A clip containing an alpha channel is included in the sample clips.)

Add a clip to a superimpose track When a clip is in a superimpose track (Video 2 or higher), you can use transparency settings to create transparent areas in which the clips in lower tracks can display through.



- To superimpose a clip over another clip, place two or more clips on top of one another in the Timeline, with at least one clip in a superimpose track.
- To add additional superimpose tracks to the Timeline, drag a clip from the Project window or Source view to the time ruler, or click the Track Options button (≡) at the bottom of the Timeline and click Add.



Drag a clip to the time ruler (left) to automatically create a new superimpose track (right).

Apply transparency Use the Transparency Settings dialog box to apply transparency to clips. For more information, see “Using keys to superimpose and create composites” on page 298. To apply transparency, do the following:


- 1 Select a clip in the superimpose track, and choose Clip > Video Options > Transparency, or click the Transparency box in the Effect Controls palette.
- 2 Select a transparency key from the Key menu. For example, if the selected clip contains an alpha channel, use the Alpha Channel key. If the clip was filmed with a colored background, choose the appropriate color key, such as Blue Screen, Green Screen, or Chroma.
- 3 Click the page peel icon (📄) under the Sample window to preview the effect of the transparency setting on your footage.
- 4 Click OK to set the transparency and return to the project.



Before (left) and after (right) transparency


Animating a still image

Using the controls in Premiere's Motion dialog box, you can move, resize, rotate, or distort any video or still image clip in your project. You can also use the Transform effect to animate, resize, rotate, or distort a clip. See online Help for more information on the Transform effect.




Creating a motion path All motion effects are located in the Motion Settings dialog box. For more information, see “Animating a clip’s motion” on page 311. To create a motion path for a clip, do the following:

- 1 Select the clip in the Timeline, and then choose Clip > Video Options > Motion or click the Motion box in the Effect Controls palette. Premiere’s default motion path is the straight horizontal line through the center of the frame.
- 2 To modify this path, click the path to add motion keyframes, and then drag them in any direction.
- 3 To adjust the time between motion keyframes, move the keyframes on the motion timeline directly below the motion path.




- To delay motion at any point in time, select a keyframe and set Delay to the time you want. A blue bar in the motion timeline represents the length of the delay from one keyframe to the next.

Rotating and resizing an image The Delay and Motion options, located at the bottom center of the dialog box, provide more control over the time between keyframes and let you create numerous visual effects.




For example, if you simply want to resize and rotate an image without moving it at all, set the Delay for the first keyframe on the path to 100%. Then, move the image thumbnail on the motion path to position the clip in the frame, and adjust the Zoom, Rotation, or Distortion settings. For more information, see “Rotating, zooming, delaying, and distorting” on page 316.



Creating final video

An overview of output options

You can output a video program using a variety of output settings and export to any number of formats. You can also take one program and create a variety of different files. For example, you can record a video program to tape, export it as a RealVideo file, export it as a DV stream, and then export it as a QuickTime streaming or hinted video. For more information, see Chapter 10, “Producing Final Video.”




Use Premiere to capture digital video directly from the camera to the computer (left) and then export a completed video piece to CD, video tape, the Web, or back to your DV camera.

Exporting to the Web


In addition to its movie export feature, Premiere includes three built-in export options that provide unique solutions for creating Web-based media: *Save for Web*, *Advanced Windows Media (Windows only)*, and *Advanced RealMedia Export*. For detailed information on each of these options, see the online Help within each plug-in's dialog box.

Export to a Web-ready file format You can take any video program in Premiere and export it as a file optimized for viewing on the Web. Do this by choosing one of the three Web export options in the File > Export Timeline menu or the File > Export Clip menu. For information on any of these plug-in export options, see the plug-in's online Help.

- Use the *Save for Web* option (a Terran Media Cleaner plug-in) to export a video program to one of a variety of Web-optimized file formats. This is a one-stop Web output option that includes presets for exporting as QuickTime hinted and streaming video, RealMedia SureStream video, ASF Intelligent Streaming video, MPEG-1 video, and MP3 audio, as well as other video and audio formats.
- Use the *Advanced Windows Media* option (Windows only) to export a video and audio (audio required) program as a Windows Media file (.WM). Windows Media files can be played back within Premiere or over the Web using the Windows Media Player, which is available as a free downloadable file from Microsoft's Web site (<http://microsoft.com>).
- Use the *Advanced RealMedia Export* option to export a video program as a RealMedia file (.RM). RealMedia is a streaming media file format that can be played back within Premiere or over the Web using the RealPlayer application, which is available as a free downloadable file from Real Networks' Web site (<http://real.com>).



What's New in Premiere 6.0



With the release of version 6.0, Adobe Premiere continues to lead the way in professional desktop video editing, introducing many new features and enhancements. Taking your video from the video camera to the Web is a clean and simple process now that Premiere directly supports IEEE 1394 (FireWire/i.Link) for both Windows and Mac OS, and includes Web-optimized export options from Terran Interactive, Microsoft, and RealNetworks. Premiere also includes over 30 After Effects plug-ins so that you can easily create visually compelling, one-of-a-kind video, and a new Audio Mixer window so that you can precisely mix your audio clips in real time!

Premiere 6.0 also provides new and improved organization tools, including Project window bins to organize your clips; the storyboard, in which you can assemble clips before adding them to the Timeline; the Automate to Timeline command, which automatically places the contents of a storyboard or bin on the Timeline; and the Settings Viewer, which you can use to compare settings for all the different elements of your project.

Robust DV support

DV functionality

Premiere 6.0 provides direct support for IEEE 1394 (FireWire/i.Link) on both Windows and Mac OS. Using only the DV port on your computer, an IEEE 1394 connection, and your DV camcorder, you get perfect digital video in Premiere. When you capture DV video, Premiere displays it at the appropriate aspect ratio so that your images won't appear distorted on your computer screen, and provides a DV editing mode so that you can preview your DV video at full quality on your DV device. Premiere also includes specific DV presets and DV device control for flawless capture from and export to your DV device.

DV presets Premiere stores groups of project settings in files called presets, which include settings for compressor, frame size, pixel aspect ratio, frame rate, color depth, audio, and fields. When you first start a project, Premiere prompts you to select a default preset or a previously saved custom preset from the Load Project Settings dialog box. If the available presets are not appropriate for your project, click Custom and select individual settings.

Now that DV is widely used by video editors, Premiere 6.0 includes DV-specific presets for NTSC and PAL that you can use with your DV equipment.


The DV-specific presets differ only in the following ways:

- NTSC or PAL
- Standard 4:3 or Widescreen (Cinema) 16:9 aspect ratio
- 32 kHz (12-bit) or 48 kHz (16-bit) audio sample rate

The presets can be customized for the following variations:


- Video rendering: standard interlaced or progressive scan
- NTSC time display: drop-frame timecode (default) or non-drop-frame timecode
- Sample rates: 32 kHz, 48 kHz, or 44.1 kHz. (Because many DV devices do not support 44.1 kHz audio, it is not included in a default preset, but it is an option under Audio Settings in the Project Settings dialog box.)

DV device control With device control you can control the videotape from within Premiere's capture window. When you select device control, you can also batch-capture video, capture from an In point to an Out point, and automatically begin recording from the tape. Premiere now includes DV device options that optimize performance and reliability for your camera or deck. Device control options are located in the Scratch Disk and Device Control preferences dialog box. For more information, see "Capturing clips with device control" on page 127.



Support for nonsquare pixels Premiere now provides support for a variety of nonsquare pixel aspect ratios, including DV's Widescreen (Cinema) pixel aspect ratio of 16:9 (1.2) and the Anamorphic pixel aspect ratio of 2:1 (2.0).

When you preview on your computer screen, Premiere displays nonsquare video with a corrected aspect ratio on the computer monitor so that the image is correct. Motion and transparency settings, as well as geometric effects, also use the proper aspect ratio, so you don't have to worry about distortions appearing after editing or rendering your video.




DV editing mode When you use the new DV Editing Mode, Premiere sends the captured or rendered video out through the IEEE 1394 connection to the DV device for previewing at full quality. Use this feature while previewing or scrubbing in any Window or while render-scrubbing (pressing Alt [Windows] or Option [Mac OS] while scrubbing) the Timeline to preview effects!

DV file interchange options Premiere now imports and exports native DV files in a variety of formats including QuickTime, Type 1 or Type 2 AVI files, and DV stream files. (DV stream refers to the bit-by-bit copy of the digital data on a DV tape, not Internet streaming.) When you print to video or export to tape, Premiere sends the DV information to your IEEE 1394 connection so you can record it on your DV device.

Capture window The Capture window has been enhanced to include all of the necessary capture tools right in the window. For more information, see “Logging clips to a batch list” on page 132.

Some of the enhancements include:

- A control panel under the preview window to control the connected playback device.
- A Settings palette that displays your current capture settings as defined in the Project Settings dialog box. If you want to change these settings, click Edit to open the Capture section of the Project Settings dialog box, and make your changes. Any changes are automatically reflected in the Settings palette.
- A Logging palette for entering In and Out points for clips to be batch-captured later. Click the Set In or Set Out buttons to set the time for In or Out at the current position of the tape in the device.



A. Log settings B. Capture settings C. Device Control controls

Web output


Built-in Web export for one-step Web output

Premiere 6.0 includes three options for exporting an individual clip, a segment of the Timeline, or the entire program to a Web-optimized file format. When you have finished editing your video program, choose File > Export Clip or File > Export Timeline and select one of the following Web export options: Save for Web, Advanced Windows Media, or Advanced RealMedia Export. Choosing one of these options opens the respective plug-in dialog box in which you can specify your exported file format information. Also included in this release is the ability to embed Web markers in your video files.

Save for Web The Save for Web export option from Terran offers several different Web output options. Now you can export any Premiere project to a Web-optimized file format by simply choosing File > Export Timeline > Save for Web. When using this option, you select a preset from the Save for Web dialog box to export to a variety of formats, including any of the following: QuickTime, RealMedia, ASF, MPEG-1, MP3, DV stream, and QuickTime DV. These formats can be played back over the Web, from your hard disk, or from a CD-ROM using a variety of player applications such as QuickTime, RealPlayer, and Premiere. For more information, see the plug-in's Online Help.


Advanced Windows Media (Windows only) Use the Windows Media option from Microsoft Corporation to export Timeline content to the Windows Media (.WM) streaming-media file format. Using the Advanced Windows Media plug-in, you can generate high-quality and high-bandwidth video that can be played over the Web, or downloaded and played back from within Premiere, Windows Media Player, or a variety of other playback applications. For more information, see the plug-in's Online Help.

Advanced RealMedia Export Use the Advanced RealMedia Export plug-in from RealNetworks to export directly to the RealMedia (.RM) streaming format or Web download format. RealMedia files (containing both RealVideo and RealAudio) can be played from the Web or downloaded to a hard disk and played over the Web using the RealPlayer application, which is available as a free downloadable file from real.com. For more information, see the plug-in's Online Help.



Web and chapter markers You can set Timeline markers that include links to HTML pages or to chapters in a QuickTime movie or DVD. During playback, these markers automatically open the linked Web content or chapter. For more information, see “Using markers” on page 185.

To create a Web or chapter marker, set a Timeline marker and then either double-click it or choose Timeline > Edit Timeline Marker to open the Marker dialog box.



Within this dialog box, do any of the following:

- In the Comments field, type text that you want to appear in your video program, in the Monitor window preview. Comments are visible only when your project is set to QuickTime editing mode. They are not exported with the project.
- In the Duration field, type the amount of time you want the comment to appear.
- In the Marker Options section, type a chapter number, such as Chapter 1, to create a jump from the project to the specified chapter in a QuickTime movie.

In the Web Links section, type a URL, such as <http://www.adobe.com/premiere>, to initiate a jump to the specified URL in your Web browser. To target a specific frame on the Web site, type an HTML target name in the Frame Target field.

Enhanced professional tools


Enhanced Monitor and Timeline windows

The enhanced Monitor window provides more efficient editing control with three-point, four-point, and six-point editing (L-cut) capabilities when using a combination of the Source and Program views. The streamlined Timeline window offers precise editing capabilities for piecing together video projects. In this window you can directly adjust opacity, add transitions or effects, and modify keyframes.

Monitor window The Monitor window retains all of its power but is much more intuitive in Premiere 6.0. For more information, see “Using the Monitor window” on page 163.

Some of the enhancements to this window include:

- Clearly defined Source and Program View windows, with separate controllers.
- Buttons at the top for toggling between Dual View, Single View, and Trim Mode.
- Customizable Title-Safe and Action-Safe margins for both the Source and Program view windows.
- Marker buttons for both the Source and Program View windows. You no longer need to go to the Clip menu to set a marker!
- Enhanced Trim mode window that includes Set Focus buttons, which let you focus on the Clip Out, the Clip In, or both; new shuttle controls to help you set Out points for the Clip Out and In points for the Clip In; Target menus in which to choose the tracks you want to trim; and new Out Shift and In Shift menus showing the number of frames that have changed between the original In or Out points and the newly marked In and Out points.




A. View buttons B. Safe Zones C. Source View controllers
D. Program View controllers

Timeline window The Timeline window has added tools and buttons to increase efficiency. For more information, see “Using the Timeline window” on page 171.

Some of the enhancements to this window include:

- All of the tools have been improved and now provide more intuitive visual feedback.
- The lower left corner contains new buttons for quick access to new and frequently used Timeline features such as Track Options Dialog, Toggle Snap to Edges, Toggle Edge Viewing, Toggle Shift Tracks Options, and Toggle Sync Mode.
- The new Toggle Shift Tracks Options button (⇧⇨) along the bottom of the window lets you decide whether a specific edit, such as a rolling edit, a ripple delete, or an insert, shifts clips on all tracks or only on the edited track.
- The Toggle Sync Mode button (⇧⇩) along the bottom of the window lets you toggle between moving linked (synched) audio and video clips independently of each other, and moving them in unison.
- Adding new tracks is as simple as dragging a clip to the time ruler or the blank space at the bottom of the window. You can also use the Track Options Dialog button (⇧⇨) at the bottom of the window to open the Track Options dialog box and quickly add one or more video or audio tracks.
- The preview area (area directly under the yellow work area bar) now displays colored preview bars: no bar indicates a cuts-only segment that can play in real time, a red bar indicates that you need to build a preview file for the segment, and a green bar indicates that a preview file exists on disk for the segment (light green represents audio previews and dark green represents video previews).
- You can replace transitions simply by dropping a new one on top of an existing one. If a transition doesn't fit in the designated area, the new Fix Transitions dialog box appears, providing clear and easy options to fix the problem.



A. Preview bar B. Keyframe icon C. Video and Audio tracks
D. Timeline quick access buttons

- By default, the work area grows with your project: as you add clips to your program, the yellow work area bar expands to cover all clips.
- Linked audio and video clips are green.
- New keyframe lines exist within each video and audio track. Once you expand a track, you can click an icon to display the Keyframe area, the Waveform, or the Opacity, Volume, and Pan rubberbands.

Clip window The Clip window includes all the features of the Source View. It includes controllers for setting In and Out points and Markers. If you open the Clip window by double-clicking a clip in the Timeline, and then make changes to the In or Out points or create new markers, an Apply button appears at the top of the window. Click Apply to apply the changes to the clip in the Timeline. For more information, see “Importing clips” on page 151.



New Timeline menu The menus have been reorganized and a new Timeline menu has been added. Now you can find any command under its associated menu. For example, under the Timeline menu are commands such as Preview, Render Work Area, Add Video Track, and Set Timeline Marker.

Expanded context menus The context menus for each window in Premiere 6.0 have been expanded to include many more commands and functions. For example, the context menu for the Source View in the Monitor window includes commands such as online Help, Properties, Speed, Open Master Clip, and Set Clip Marker.

Audio Mixer


Now you can process audio within Premiere using a professional-level mixing tool: the Audio Mixer. This tool resembles a traditional multichannel mixer, featuring gain and pan adjustment for up to 99 audio tracks. The Audio Mixer works in conjunction with the Monitor window, so you can make adjustments as you play the audio and watch the synchronized video in the Monitor window. For more information on the Audio Mixer, see “Working with the Audio Mixer window” on page 263.

Audio tracks Each audio track in the Audio Mixer is numbered or named the same as its corresponding track in the Timeline. A Master fader track is displayed along the right side of the Audio Mixer window. The Master fader represents the final mix of the combined audio tracks. The volume for this track is computed after mixing all the audio tracks together and applying the output gain value. The mono/stereo format for the Master fader is determined by your project settings: if your project is set up for mono, the Audio Mixer provides a mono VU meter; if your project is set up for stereo, the Audio Mixer provides a stereo VU meter.



The following controls are available when mixing audio tracks:

- Select Mute to temporarily turn off a track. You cannot modify the parameters for a track when it is set to Mute.
- Select Solo to temporarily mute other tracks. Multiple tracks can be set to Solo at one time.
- Right-click (Windows) or Control-click (Mac OS) a track's volume fader and select a Gang option from the context menu that appears. Then select the same gang option for another track. When tracks are ganged, the relative volume fader positions between them are preserved—when you move one ganged track's volume fader, the other track's fader moves as well.



Automating the mixing process Use the automation buttons to control how Premiere handles your adjustments for each track (for more information, see “Working with the Audio Mixer window” on page 263):


- Click Automation Read (⏮) to have Premiere read the previously stored volume and pan values.
- Click Automation Write (⏺) to have Premiere read the stored volume and pan values, and write (record) the changes you make in the mixer.
- Click Automation Off (⊗) to ignore any stored values and read only those you set in the mixer.

Use the options in the Audio Mixer Options dialog box (Window > Window Options > Audio Mixer Window Options) to determine how the Mixer handles the Automation Write process (for more information, see “Adjusting audio levels in the Audio Mixer window using automation” on page 266):

- Select Touch to write (record) changes only when you are dragging or holding the control in the Mixer.
- Select Latch to write (record) changes during and after you move the control in the Mixer.
- Select Write to always write (record). This option begins writing (recording) from the playback start location of the fader.
- Select Write/Touch when you want to use the Write option until you stop the playback, at which point you write (record) only when you move the fader.

VU meters Each track has a separate VU Meter. When the audio is clipping, the Clip Indicator at the top of the meter lights up. (Clipping occurs when the volume reaches or exceeds 0 db for 3 consecutive seconds. If you don't lower the volume so it is within the clipping threshold, data will be lost.) Click the Clip Indicator light to turn it off.

Volume faders Each track has a separate volume fader. Drag the fader up to increase volume; drag down to decrease volume. When you select Automation Write, changes you make to the volume fader are reflected by handles on the clip's Volume rubberband in the Timeline.



Pan controls Each track also has a separate Pan control. Panning is available only when your project's Audio setting is Stereo. To pan audio, turn the Pan control to position sound to any degree between 100% to the left or 100% to the right. If a clip is mono, pan to shift the position of the sound within the project's stereo field. If a clip is stereo, pan to balance the amount of sound in the left and right channels.



When Automation Write is selected, changes you make to the Pan control are reflected by handles along the Pan rubberband in the Timeline.

Improved project management


Manage all of a project's media using the flexible Project window. Create multiple bins for organizing clips in a split-view project window; set the poster frame for a video clip; even preview the clip in a project thumbnail preview window. The new Project Settings dialog box offers presets for common video formats. The new Settings Viewer displays all settings (including capture, project, and export) in one screen and compares them to the clips in the project so that you can easily spot problems.

Project window The Project window now includes a Preview area; when you select a clip in the Project window, Premiere displays the clip's thumbnail along with file information. To play the thumbnail preview, click the play button (▶) under the preview to play a video clip, and click it again to stop. If you want to change a clip's poster frame (the frame Premiere uses as an icon to represent the clip), scrub through the video preview until you find the frame you want to use and then click the poster frame button (Ⓜ).



A. Thumbnail preview B. Play button C. Poster frame button


Premiere's new Bin area provides a hierarchical presentation of files in your project. Click a bin to see its contents. Every project uses at least one bin. You can create new bins, nest bins within one another, and save bins to your hard disk as files for use in other projects. For more information, see "Customizing a Project or Bin window display" on page 94.



A. Bin B. Find C. New Bin D. Create Item E. Delete Selected Items F. Resize Bin Area

The Project window also includes several new command buttons at the bottom left of the window:

- Click the new Find button (🔍) to search for files in the open project. You can search by any number of parameters.
- Click the New Bin button (📁) to create a new bin. You can then drag files to the bin or import directly to the bin.
- Click the Create Item button (📄) to create a new title, offline file, color matte, black video, bars and tone, or universal counting leader.
- Click the Delete Selected Items button (🗑️) to delete the selected bin or file.
- Drag the Resize Bin Area button to increase or decrease the size of the Bin area.



Load Project Settings dialog box at startup When you launch Premiere 6.0, the first dialog box you see is Load Project Settings. This dialog box contains presets for the most commonly used default project settings, including eight DV-specific sets. If you have a capture card installed that includes its own preset, that preset will be listed as well. If you choose not to use a default preset, click Custom and select your own settings. You can save your customized settings for use as a preset. For more information, see "Specifying project settings" on page 74.

Settings Viewer Because matched settings are such an important part of your video project, the Settings Viewer clearly displays all settings in one window. Settings that do not match appear red. To open this window, choose Project > Settings Viewer.

Use this window to ensure that your capture, project, and clip settings are the same throughout your project. Discrepancies between capture, project, and clip settings can cause unexpected behavior in your previews and final output. It's best to use the project and capture settings recommended or supplied by your capture card manufacturer. Export settings will always match your project settings until you change them, and you can change them to anything you want. For example, your capture, project, and clip settings may use a frame size of 720 x 480, but you can export the project as a RealVideo file with a 320 x 240 frame size.

If a setting appears red, double-click it and make the appropriate changes in the settings dialog box that appears. For more information, see “Comparing settings using the Settings Viewer” on page 82.


	Capture Settings	Project Settings	boxcar's avi	Export Settings
Video				
Mode:	Microsoft AVI	Microsoft AVI	Microsoft AVI	Microsoft AVI
Compressor:	DivX4 Codec by Real...	DivX4 Codec by Real...	Microsoft MPEG-4 V1...	DivX4 Codec by Real...
Frame Size:	640 x 480	360 x 240	360 x 240	360 x 240
Frame Rate:	29.97 FPS	29.97 FPS	10.00 FPS	29.97 FPS
Sample Rate:	MilliSec	MilliSec	MilliSec	MilliSec
Quality:	100 %	100 %	100 %	100 %
Pixel Aspect Ratio:	Square Pixels (1.0)	Square Pixels (1.0)	Square Pixels (1.0)	Square Pixels (1.0)
Audio				
Sample Rate:	44100 Hz	44100 Hz	n/a	44100 Hz
Format:	16 Bit - Stereo	16 Bit - Stereo	n/a	16 Bit - Stereo
Compressor:	Uncompressed	Uncompressed	n/a	Uncompressed
Render				
Field Settings:	No Fields	No Fields	No Fields	No Fields

Visualization tools

Premiere offers a number of new and enhanced features to help increase your productivity. With the new Storyboard window and its Automate to Timeline command, you can quickly visualize and implement the layout of clips in your project. The Automate to Timeline provides a quick and easy way to transfer all the clips in a Project window bin or storyboard to the Timeline. The Commands palette has been updated and enhanced with increased functionality and organization features.

Storyboard Use the storyboard to arrange clips before adding them into the Timeline. Double-click a file in the storyboard to change its In or Out points, add markers, or include audio or video. Once you have your clips in order, automatically transfer them to the Timeline using the Automate to Timeline command, adding transitions between the clips if desired, or print the storyboard directly to the selected video output device.

With the context menu for the Storyboard window, you can locate the source clip, add the clip to the project, and change the speed of a video clip or the duration of a still clip. To access the context menu, right-click (Windows) or Control-click (Mac OS) the clip icon in the Storyboard window. For more information, see “Creating a storyboard” on page 203.




A. Sequence direction marker B. Clip information
C. End of sequence marker D. Automate to Timeline button E. Print to Video button

Automate to Timeline command Use this command to automatically transfer the contents of a storyboard or a Project window bin to the Timeline. The Automate to Timeline dialog box offers several options for placing the clips in the Timeline, including selection of contents to place and the sorting order of the contents; the placement preference (sequentially or at unnumbered markers); insertion location; and the use of transitions between clips.


To place clips at unnumbered markers, create a series of unnumbered Timeline markers (see “Using markers” on page 185), positioning them at the exact location where you want the clips to appear. You can choose to stretch clips to fill the space between markers or leave gaps between clips; clips that are longer than the duration between markers are automatically shortened.

To transfer a storyboard, click the Automate to Timeline button (⇨) in the Storyboard window or choose Automate to Timeline from the Storyboard window menu, the Project menu, or the Storyboard window’s context menu.

To transfer a sequence from a bin, choose Automate to Timeline from the Project window menu or the Project menu. For more information, see “Adding multiple clips using an automated process” on page 201.



Commands palette This palette has been updated and enhanced with increased functionality and organization features. When you select Button Mode in the palette menu, the commands appear in the colors you’ve designated. When you deselect Button Mode, you can add, delete, and change commands. When you are adding or changing a command, the new Function Key menu provides a list of all available keys. New buttons at the bottom of the palette provide quick access for playing a command (▶), adding a command (⊞), and deleting a command (🗑). For more information, see “Using the Commands palette” on page 102.




*Button Mode selected (left) and deselected (right).
A. Play Command B. Add Command C. Delete Command*


Enhanced effect support

Premiere 6.0 has changed the way you add effects and transitions to video and audio. The new palettes provide easy access to all effects and transitions, and better organization. With the Effect Controls palette, you can manage all your effects from one location, and the Timeline window's new keyframe track provides you with a visual representation of where effect keyframes are in the clips.

Video, Audio, and Transition palettes The Video Effects, Audio Effects, and Transitions palettes are now organized by folders, which you can rename, reorganize, hide, or delete. For more information, see “Working with effects” on page 326.




To hide folders or files, select a folder or file and choose Hide Selected from the palette menu; to reorganize the content within a folder, drag files from one folder to another; and to remove folders, select the folder and choose Delete Folder from the palette menu. If you forget where you've moved an effect, locate it using the Find button (🔍) at the bottom of the palette.




Applying effects and transitions To apply an effect or transition, drag the effect or transition from the palette to the clip in the Timeline. To delete an effect, select it in the Effect Controls palette and click the Delete button (🗑️). To delete a transition, select it and press the Delete key.

Effect Controls palette This palette is similar to the Adobe After Effects Effect Controls palette. To open it, choose Window > Show Effect Controls. Use this palette to manage your effects: enable or disable keyframing, adjust settings, hide or show, and delete. The palette contains information on every effect applied to clips in your video program as well as any motion or transparency settings you've applied. To see an effect and its settings in the Effect Controls palette, select the clip in the Timeline. All the effects for the selected clip appear in the palette.



Some effects, including those from After Effects, do not use a Settings dialog box, so always check the Effect Controls palette for adjustable settings when applying an effect. For more information, see “Applying and controlling effects” on page 327.

Effect Keyframes Premiere uses keyframes to change an effect's behavior over time. Now you can add the keyframes directly in the Timeline, using the new Effect Keyframe area underneath each clip. Setting keyframes in the Timeline allows you to see when an effect's settings change relative to the entire program. You can also quickly edit and preview the settings at each keyframe. For more information, see “Working with keyframes” on page 324.



Customizable workspace

Depending on the type of work you are doing in Premiere, you may want to hide or display certain window features and palettes. This arrangement of windows is called the “workspace.” When you start Premiere 6.0 for the first time, you choose the workspace that you want to work within. You can choose a new workspace option from the **Window > Workspace** menu. You can also rearrange the workspace and save it as a custom workspace. Workspaces do not limit how you use the windows and palettes, since you can alter their arrangement at any time. For example, if you’re using the A/B Editing workspace, you can choose **Dual View** from the **Monitor** window menu to display the Source view. For more information, see “Selecting an editing workspace” on page 169.


A/B Editing workspace If you want to work in a simple A/B roll environment, you can now simplify the work area by choosing the A/B Editing workspace:

- The **Monitor** window uses the **Single View**, displaying only the **Program View** window and controllers. Individual clips open in separate **Clip** windows.
- The **Timeline** window displays the **Video 1A** track expanded, with the **transition** track showing between **Video 1A** and **Video 1B**.



Single-Track Editing workspace If you prefer to use professional editing techniques and work with the Video 1 track as a single track, you'll want to use the Single-Track Editing workspace:

- The Monitor window displays both the Source View and the Program View.
- The Timeline window has a single Video 1 track. You can expand the Video 1 track to show the transition track and the A and B tracks.



Audio workspace The Audio workspace uses your current workspace (A/B Editing or Single-Track Editing) with the following adjustments: clips open in a separate Clip window, the Audio Mixer is open, and no palettes are displayed.

Effects workspace The Effects workspace uses your current workspace (A/B Editing or Single-Track Editing) with the following adjustments: the Monitor window displays in Single view, and the Effect Controls, Navigator, and Transitions palettes are active.


Custom workspaces You can create your own custom workspace that combines your favorite features of the different default workspaces. Premiere offers unprecedented flexibility for you to choose your own work environment. Custom workspaces that take advantage of dual monitors can also be saved. Dual-monitor configurations offer additional flexibility and the added benefit of having more windows and palettes open and accessible.

Integration

New tools and a more familiar interface


Premiere now provides the *Edit Original* command so that you can quickly edit content that was created in another program. And the *Adobe History* palette makes experimenting with video edits and effects a carefree process! Premiere has also thoroughly integrated the Adobe interface familiar to those who have worked in other Adobe applications such as *Adobe Photoshop* and *Adobe Illustrator*.

Edit Original command The *Edit Original* command opens clips in their original application so that you can edit them and then update them in the Timeline without exiting Premiere or replacing the files. The *Edit Original* command works with any application installed on your hard disk. For example, if you want to edit a clip that you created in *After Effects*, *Photoshop*, *Illustrator*, or *Premiere*, select the clip in your project and choose *Edit > Edit Original*. After you make and save changes in the original application, Premiere automatically incorporates those changes in your current project. To export a Premiere project with the information necessary to use the *Edit Original* command, choose *Project Link* from the *Embedding Options* menu in the *Export Settings* dialog box. For more information, see “*Editing clips*” on page 189.



History palette Premiere's new History palette adds a new dimension to the Undo/Redo command. Use this palette to preview your project at a previous state. You can choose to delete all edits after the selected state, return to your current state, or incrementally restore states.

All states created during your current working session are listed in the History palette. If you jump to a state earlier in your project, all the following states are dimmed in the palette, and Premiere deletes them if you resume editing. You can manually delete them by clicking the Trash button (🗑) or choosing Delete from the History palette menu. When you close a project, all states are removed from the History palette. For more information, see "Using the History palette" on page 104.



Selecting a state temporarily removes the effects for all succeeding states.

Adobe After Effects plug-in integration Premiere 6.0 has incorporated many effects from Adobe After Effects 4.1. After Effects video effects are listed with the Premiere effects in the Video Effects palette, and include the After Effects symbol next to the name (Ⓜ). Some After Effects video effects replace similar Premiere effects; the replaced Premiere effects are located in the Obsolete folder in the Video Effects palette. If you open a project from Premiere 5.0 and need to use a replaced effect, choose Show Hidden from the Video Effect palette menu to access the obsolete effects. For more information, see "Using After Effects effects" on page 332.

Familiar Adobe interface The Premiere interface resembles the award-winning standard Adobe interface used by other Adobe products such as Adobe Photoshop and Adobe Illustrator. The similarities make it easy to move between Adobe programs with efficiency and ease.

http://



1



Chapter 1: Working with Projects

A *project* is a single Premiere file that describes a video program. It stores references to all the clips in that file and contains information about how you arranged the clips. It also includes details of any transitions or effects you applied. You can add and remove clips, organize clips into bins within the project, and substitute low-resolution clips as placeholders for your final, high-resolution clips.

Selecting an initial workspace

When you start Premiere for the first time (or when the Preferences file has been deleted), Premiere asks you to select an initial workspace. Based on your decision, Premiere optimizes the layout you will use to assemble and edit programs. Your choice of workspace depends on the kind of editing you will be doing.

If you will primarily be dragging clips from the Project window to the Timeline, select the A/B Editing workspace. If you will be using more advanced editing techniques such as three- or four-point editing, select the Single-Track Editing workspace. For more information, see “Customizable workspace” on page 67 and “Selecting an editing workspace” on page 169.

Starting a project

Start a new project by specifying project settings. It’s a good idea to save the project immediately afterward. See “Saving and autosaving a project” on page 83.

To start a new project:

- 1 Do one of the following:
 - If Premiere is not open, start Premiere.
 - If Premiere is already open, choose File > New Project.

2 When the Load Project Settings dialog box appears, do one of the following:

- To apply preset project settings, select an item from the list of Available Presets and click OK.
- To customize settings, choose the preset that most closely matches your editing environment, and then click Custom, select your specific project settings, and click OK. See “Saving and loading project settings” on page 82.

Specifying project settings

When you start a project, review the project settings, which are organized into five categories:

General Settings Control the fundamental characteristics of the video program, including the method Premiere uses to process video (Editing Mode), count time (Time Display), and play back video (Timebase). See “General settings” on page 75.

Video Settings Control the frame size, picture quality, compression settings, and aspect ratios that Premiere uses when you play back video from the Timeline (the window where you edit your video program). See “Video settings” on page 77.

Audio Settings Control the characteristics of audio you play back from the Timeline. See “Audio settings” on page 78.

Keyframe and Rendering Options Control frame-related characteristics when you build (render) and play back video previews from the Timeline. These options work in combination with the Video settings. See “Keyframe and rendering options” on page 80.

Capture Settings Control how Premiere transfers video and audio directly from a deck or camera. (Other Project Settings panels do not affect capturing.) For more information about capture settings, see “Digitizing analog video as DV” on page 113 and “Preparing for DV video capture” on page 120.

The appropriate settings for your project are usually determined by the current stage of your project. Many video capture cards provide their own presets or recommend project settings for optimal results. For information on comparing and changing settings, see “Comparing settings using the Settings Viewer” on page 82. Keep the following guidelines in mind as you progress through your project:

- When setting up or editing a project, specify settings that will provide the quality you want when you play back the Timeline. For example, specify project settings that match the requirements of the final program or that temporarily lower the frame rate so that your computer can process edits faster. For more information on using low-resolution files, see “About offline editing” on page 111.
- If you are about to use a videotape deck to record directly from the Timeline, specify project settings that represent the final picture quality you want.
- If you are about to export the video program to a file (for example, a QuickTime .MOV file) and you want to specify different settings than you did for editing, you must also specify export settings. Export settings are available through the File > Export Timeline command, not in the Project Settings dialog box. Since you use separate settings for previewing and exporting, you can also maintain a set of preview settings that stays constant no matter how often you change export settings (such as when you repurpose a program for multiple distribution media such as television and the Web). When you specify project settings for the first time, the settings are copied to the export settings, making your export settings the same as your project settings unless you change the project or export settings later. See “Exporting a video” on page 346.

General settings

Choose Project > Project Settings > General, to specify the following options:

Editing Mode Determines which video method is used to play video back from the Timeline and which compression methods are listed in the Video Settings panel. The QuickTime editing mode is installed with Premiere. In Windows, the Video for Windows and DV Playback editing modes are also installed. Manufacturers of video-capture cards or other video hardware may provide plug-in software that adds editing modes for maximum quality and compatibility with their hardware.

***Note:** The Editing Mode does not necessarily specify the export format. For more information, see “Exporting a video” on page 346.*

Advanced Settings This button may be available if you have installed an editing mode plug-in provided by another manufacturer. For information on settings for your plug-in editing mode, see the documentation provided by the plug-in's manufacturer.

Timebase Specifies the time divisions Premiere uses to calculate the time position of each edit. In general, choose 24 for editing motion-picture film, 25 for editing PAL (European standard) and SECAM video, 29.97 for editing NTSC (North American standard) video, or 30 for other video types. Do not confuse timebase with the *frame rate* of the video you play back or export from the Timeline, although timebase and frame rate often use the same value.

Playback Settings This button is available when you use a DV preset or choose the DV editing mode (Windows) or QuickTime editing mode (Mac OS), or if you have installed a plug-in that provides additional playback functions. When you use the DV (Windows) or QuickTime (Mac OS) editing mode, use this option to indicate where you want your previews to play back: on your DV camcorder or other connected device, or on your desktop. For information on the playback settings available for third-party plug-ins, see the documentation provided by the manufacturer of the plug-in.

Time Display Specifies the way time is displayed throughout the project. The time display options correspond to standards for editing video and motion-picture film. For broadcast NTSC video, choose 30 fps Drop-Frame Timecode if that was the time display used by the original video. For video to be played back from the Web or CD-ROM, choose 30 fps Non Drop-Frame Timecode. For PAL and SECAM video, choose 25 fps Timecode. For motion-picture film, choose Feet + Frames 16mm or Feet + Frames 35mm. To count individual frames and audio samples instead of timecode, choose Frames/Samples.

Current Settings Displays a summary of the settings you specified in all Project Settings panels.

Video settings

Choose Project > Project Settings > Video, to specify the following options:

Compressor Specifies the *codec* (compressor/decompressor) for Premiere to apply when building a preview of the Timeline. The codecs available depend on the Editing Mode specified by your preset or selected in the General Settings panel. Click Configure (if available) to set options specific to the selected codec. If you chose an editing mode provided by a manufacturer of a video-capture card or other hardware, see the documentation for the hardware, as it may recommend a particular codec for editing with that hardware. Otherwise, consider choosing a fast codec so that edits are processed quickly. If you want to play video back through your capture card to an NTSC or PAL monitor, choose the codec specific to your capture card.

Note: If you use a clip in your video program without applying effects or changing frame or time characteristics, Premiere uses the clip's original codec for playback. If you make changes that require recalculation of each frame, Premiere applies the codec you choose here.

Depth Indicates the color bit depth, or number of colors to include in video played back from the Timeline. This button may not be available if the selected compressor provides only one option for bit depth. You can also specify an 8-bit (256-color) palette when preparing a video program for 8-bit color playback, such as for the Web or for some presentation software. The Palette button may be available when 256 Colors is chosen, if the selected Editing Mode and Compressor support creating custom palettes. When the button is available, click it and then either select Make Palette from Movie (to derive a color palette from the frames used in the video program) or Load Palette Now (to import a color palette you prepared and saved previously). You can load color palettes stored in the .ACO (Photoshop color swatch), .ACT (Photoshop color palette), or .PAL (Windows palette—Windows only) format.

Frame Size Specifies the dimensions, in pixels, for frames when you play back video from the Timeline. Ideally, you want the frame size for your project to match the frame size of your video clips. A large frame size shows more detail but requires more processing. If preview playback is slow, you can reduce the frame size to a smaller dimension, as long as your capture card supports it. When changing the frame size, keep the dimensions proportional to the original video clip.

4:3 Aspect If you're using analog captured video, select 4:3 Aspect to constrain the frame size to the 4:3 aspect ratio used by conventional television. If you are using a D1/DV NTSC pixel aspect ratio, do not select this option.

Frame Rate Indicates the number of frames per second to play back video from the Timeline. In general, type a value that matches the frame rate of the final video, or type a lower value to process previews faster. When changing the frame rate, make sure that the new rate is evenly divisible by the original rate. For example, if your original frame rate is 29.97, lower it to 14.985, or if it is 30 fps, lower it to 15 or 10 fps.

Pixel Aspect Ratio Sets the aspect ratio for individual pixels. Choose Square Pixels for analog video, scanned images, and computer-generated graphics, or choose the format used by your video. If you use a pixel aspect ratio that is different from your video, the video may play back and render with distortion. For more information, see “About D1, DV, and various pixel aspect ratios” on page 147.

Quality Affects the picture quality and disk space used when you play back video from the Timeline. Low quality usually plays faster and uses less disk space, and may be preferable for editing. High quality provides the best-looking image the selected compressor can provide, but requires more disk space. You can change the quality setting while working on a project without causing distortions or affecting the final output. Some codecs, such as DV codecs, use a fixed quality level and do not provide access to this option.

Data Rate If available for the selected compressor, places an upper limit on the amount of video data that Premiere compiles for previews. Do not set the data rate higher than the data transfer capacity of your system. Select Limit Data Rate to _ K/Sec and type the data rate required. If previews do not play smoothly, reduce this value. By default, Premiere recompresses frames that use different settings than those selected in the Video settings dialog box. Select Always from the Recompress menu to compress every frame even if it is already within the data rate, or select Maintain Data Rate to preserve quality by compressing only the frames that are above the specified data rate.

Audio settings

Choose Project > Project Settings > Audio, to specify the following options:

Rate In general, higher rates provide better audio quality when you play audio back from the Timeline, but they require more disk space and processing. Resampling, or setting a different rate from the original audio, also requires additional processing time and affects the quality; try to capture audio at the final rate. Note that with DV audio, you can capture only at the rate that was originally used to record the audio. In this case, it's best to match the predominant rate of the clips in your project. If you want to use a different rate in your final output, you can export at a different rate to resample, or you can change the rate in the project preset when you are done editing.

Format Higher bit depths and stereo provide better quality but require more disk space and processing.

Compressor Specifies the codec for Premiere to apply when playing audio back from the Timeline. The codecs available depend on the Editing Mode you specified in the General panel in the Project Settings dialog box. Click Advanced Settings (if available) to set options specific to the selected codec. Generally, you don't want to compress audio for playback from the Timeline; instead, compress audio when exporting.

Interleave Specifies how often audio information is inserted among the video frames in the preview file that is created when you play audio back from the Timeline. This value is set by the preset you choose and generally does not require adjusting. A value of 1 frame means that when Premiere plays back a frame, the audio for the duration of that frame is loaded into RAM so that it can play until the next frame appears. If the audio breaks up when playing, the interleave value may be causing the computer to process too much audio at once. Decreasing the value makes Premiere store longer segments that need to be processed less often, but it requires more RAM.

Enhanced Rate Conversion When you play audio back from the Timeline, this option specifies a level of quality for converting the sample rates of clips in the Timeline to the sample rate you specified in the Rate and Format options. Enhanced Rate Conversion controls both rate upsampling and downsampling. The Off option resamples audio the fastest, but produces moderate quality. The Better option balances quality and processing time. The Best option resamples audio for the highest possible quality but requires the most processing time. Because this option can affect playback performance, you may want to select Off while editing, and then select Better or Best for the final render after you have finished editing or when you are exporting.

Use Logarithmic Audio Fades Controls how audio gain increases or decreases are perceived during playback in Premiere. Select this option to process gain levels using the logarithmic scale used by the human ear and by conventional volume controls. Deselect this option to process gain changes using a linear curve. Selecting this option creates more natural-sounding changes as sounds become louder or softer, but increases audio processing time. Audio faders in the Timeline are not changed except as a result of this option's processing of the overall gain level.

Create Audio Preview Files If There Are _ or More Specifies when Premiere creates an audio preview instead of real-time playback, based on how many audio tracks are active and how many audio effects are applied in those tracks. The number of audio tracks active and effects applied directly affects the load on your system resources. When your system resources are exceeded by audio processing demands, you will hear pops and clicks while playing back audio in Premiere. If you encounter this problem, decrease the settings for these parameters so that Premiere creates audio preview files instead of trying to process more than it can handle.

Keyframe and rendering options

Choose Project > Project Settings > Keyframe and Rendering to specify the following options:

Ignore Audio Effects Select to render audio without applied audio effects.

Ignore Video Effects Select to render video without applied video effects.

Ignore Audio Rubber Bands Select to render audio excluding changes made to the Timeline's rubberband controls for audio fading and audio panning.

Optimize Stills Select to use still images efficiently when rendering video. For example, if a still image has a duration of 2 seconds in a project set to 30 frames per second, Premiere will create one 2-second frame instead of 60 frames at 1/30 of a second. Deselect this option if the exported video file exhibits playback problems when displaying the still images. This option is determined by your preset. Some capture cards do not support optimized stills—if you are using a preset provided by your capture card, do not adjust this setting.

Frames Only at Markers Select when you want to render only the frames at which you have added a marker in the Timeline. This option does not affect compression keyframes.

Preview Choose To Screen when you want to preview edits, transitions, and effects but don't care if the preview is at final playback speed. When To Screen is selected, Premiere renders directly to the screen as quickly as possible. Playback speed depends on image size and resolution, the number and complexity of effects and transitions, and the processing speed of your system. This option is not recommended for previewing areas that include many effects. Choose From Disk when you want to preview edits, transitions, and effects at the final playback speed. With this option selected, Premiere renders the preview to the hard disk. Choose From RAM when you want to preview edits, transitions, and effects quickly, without having to first render a preview file. When From RAM is selected,

Premiere creates a preview by displaying frames as they are rendered. Because frames are rendered in RAM, this process depends on the amount of RAM available. If sufficient RAM is not available or if the frame rate, frame size, or effects used require more RAM than is available, frames may be dropped during playback, or Premiere may render the preview to disk instead. To minimize the effects of limited RAM, use a smaller frame size (for example, 320 x 240 or 240 x 180). A smaller frame size also produces a more even frame rate during Preview to RAM. If you have chosen From RAM or To Screen, you can speed up previewing by choosing 1:2 or 1:4 to reduce resolution. Choose 1:1 for normal resolution. To preview with the selected option, choose Timeline > Preview or press Enter (Windows) or Return (Mac OS). To stop a preview, press the spacebar.

Field settings Select an option that matches the playback display. This option is set by your preset. If you use a preset provided by your capture card, do not change this setting. No Fields is the default and is the equivalent of progressive scan. Some DV cameras offer a “frame movie mode,” which resembles progressive scan. If you shot your video using this mode, or if you’re using video that is anything other than interlaced, use No Fields. Select Lower Field First for interlaced DV video to maximize motion smoothness. For analog video, select either Upper Field First or Lower Field First, depending on your capture card specifications, when your final output will be played back on a television monitor using an interlaced standard such as NTSC, PAL, or SECAM. Choosing the wrong field settings causes the video to flicker or appear jagged when rendered and played back on an NTSC monitor.

Some codecs support compression keyframes, which can increase the effectiveness of compression by acting as starting points for temporal compression. Temporal compression looks for ways to compact the description of the changes during a sequence of frames. It does this by looking for patterns and repetition over time. If the codec you specified supports compression keyframes, the following Keyframe Options are available:

Keyframe Every _ Frames Select and type the number of frames after which the codec will create a compression keyframe when exporting video.

Add Keyframes at Markers Select to create a compression keyframe at each marker.

Add Keyframes at Edits Select to create a compression keyframe between each clip.

For information on the Capture Settings dialog box, see “Preparing for analog capture” on page 117 or “Preparing for DV video capture” on page 120.

Saving and loading project settings

Use the Save and Load buttons in the Project Settings dialog box to save all project settings into a file and later load them into a new project. Premiere comes equipped with settings files preset for typical programs, which you can adapt and save for your own projects. Most certified video-capture cards include preset settings files for Premiere. Adobe strongly recommends that if your capture card provides a preset file, you use it and do not manually change the settings. For information about loading saved settings, see “Starting a project” on page 73.

To save the custom settings as a preset for use in other projects:

- 1 In the New Project Settings dialog box, specify your settings, and then click Save.
- 2 In the Save Project Settings dialog box, type a name and description (if desired) and click OK. The settings are saved as a preset file that appears in the list of available presets in the Load Project Settings dialog box.

 *Save and name your project settings even if you plan to use them in only one project. Saving settings creates a backup copy of the settings in case someone accidentally alters the current project settings. These preset files are stored in the Settings folder in the Premiere folder on your hard disk, so you can back them up and distribute them if you want.*


Comparing settings using the Settings Viewer

Premiere stores settings for projects and clips, as well as settings used when you export or capture files. To make it easier to see and compare settings, Premiere displays all settings together in the Settings Viewer window. Settings that do not match display in red. Avoid potential conflicts by matching settings for each of the four categories wherever possible. You can change Capture, Project, and Export settings by clicking the associated setting heading in the Settings Viewer window.

To view, compare, and adjust settings in the Settings Viewer:

- 1 Choose Project > Settings Viewer.
- 2 Compare settings and ensure that they are the same in each category. Settings that do not match are red.

- 3 To view the settings for different clips in your project, select a clip from the clip heading, which is also a pop-up menu.



- 4 To change a setting, click the setting's heading (for example, click Project Settings), locate the setting in the dialog box that appears (you may need to navigate to different panels within a dialog box), change the setting, and then click OK.
- 5 Click OK when you are done comparing settings.

Saving and autosaving a project

Saving a project saves your editing decisions, references to source files, and the most recent arrangement of the program's windows. Protect your work by saving often. If you prefer, Premiere can save your project automatically at a specified interval. Premiere can either save the project to the same file each time or to a new file. For example, you can set Premiere to save a new archive of your project every 15 minutes, producing a series of files that represent the state of your project at each interval. In this way, automatic archiving can serve as an alternate form of the Undo command, depending on how much the project changed between each save. Because project files are quite small compared to source video files, archiving many iterations of a project consumes relatively little disk space. Adobe recommends saving project files to the same drive as your application. Archived files are saved in the Project-Archive folder inside the Adobe Premiere 6.0 folder. For information about other ways of returning to earlier versions of a project, see "Correcting mistakes" on page 89.

To save a project:

Do one of the following:

- Choose File > Save. If necessary, specify a location and filename, and click Save.
- To save a copy of a project under a new name or location and continue working in the new *copy* of the project, choose File > Save As, specify a location and filename, and click Save.
- To save a copy of a project under a new name or location but continue working in the *original* project, choose File > Save a Copy, specify a location and filename, and click Save.

To automatically save a project or series of projects:

- 1 Choose Edit > Preferences > Auto Save and Undo.
- 2 Do any of the following, and then click OK:
 - In the Auto Save section, select Automatically Save Projects, and type the number of minutes after which Premiere will save the project.
 - In the Project Archive section, type a number for Maximum Files in Archive to specify how many copies of project files from all projects will be saved into the Project-Archive folder. When the limit is reached, Premiere deletes the oldest project file to make room for the newest one. Type a number for the Maximum Project Versions to specify how many versions of each project file you want to save. For example, to save the last five versions of each project you work with, type 5.

To open an autosaved project file:

- 1 If a project is currently open, close it.
- 2 Choose File > Open.
- 3 Locate and double-click the Project-Archive folder in the folder containing Premiere.
- 4 Select a project file, and click Open. If no files are available, the autosave feature may be turned off; see the previous procedure.

Opening a project

You can open only one project at a time. Premiere recognizes Premiere project files created using versions 4.2 or later on Windows or Mac OS. See “Using a Premiere project on another platform” on page 87.

To open an existing Premiere project:

Choose File > Open. Locate and select the file, and then click Open.

Premiere doesn't copy the original source file into the project—it stores only a reference to the source file based on its filename and location at the time you imported it. If you move, rename, or delete a source file after you import it, Premiere will be unable to find it the next time you open the project. In this case, Premiere displays the Locate File dialog box, listing the missing file. You can resolve this situation using the options explained below.

OK (Windows) or Open (Mac OS) Replaces the missing file if you first use this dialog box to locate and select the original file or its replacement, and then click this button.

Offline Replaces the missing file with an *offline file*, a blank placeholder that preserves all references to the missing file throughout the project until you replace the offline file with the original file.

All Offline Replaces all missing files with offline files, without asking you for confirmation.

Skip Removes all references to the missing file throughout the project. All instances of the clip will disappear from the Project and Timeline windows.

Skip All Removes all references to all missing files throughout the project, without asking you for confirmation. See Skip.

Important: Select *Skip* or *Skip All* only when you are certain that you want to rework all the instances where the file is used in the project. If you want to keep the file in the project but can't locate it at the moment, use *Offline* instead.

Skip Preview Files Skips preview files if they cannot be found by their original path and file name. Preview files that can be found by their original path and file name are loaded automatically.

When you want to replace an offline file after the project is open, you don't have to close the project and then open it again. Instead, use the Replace Files command. For more information, see "Using offline files" on page 158.

***Note:** Because a clip is only a reference to its source file, do not delete source files while you are using them as clips in a Premiere project. After you deliver the final movie, you can delete source files if you do not plan to edit the project or use the source files again.*

Removing unused frames from source clips

Editing a video program means putting the best segments of the original clips into the program. Sometimes, the clips you use in the final program are only small portions of the original clips. Because video clips can take up large amounts of hard disk space, you can trim the project so that unused frames are removed. Project trimming is especially useful before archiving a completed project.

When you trim a project, Adobe Premiere first creates a copy of the project. In the new project, each clip's original In and Out points become the new beginning and ending of the clip, respectively. Clips that weren't used in the original project aren't copied into the new project. Premiere can also create trimmed copies of the source clips. You can preserve extra frames (called handles) before the In point and after the Out point of each trimmed clip.

To trim a project:

- 1 With a project open, choose Project > Utilities > Project Trimmer.
- 2 Select Create Trimmed Batch List to create a batch list that can be used to redigitize the trimmed versions of the clips. For more information, see "Creating a batch list to redigitize project clips" on page 137.
- 3 Select Copy Trimmed Source Files to make new copies of existing source files that include only the frames used in the Timeline plus handles as specified below.
- 4 For Keep _ Frame Handles, type the number of frames to retain before the In point and after the Out point of each clip so that edits can still be adjusted later.

***Note:** Adding handles after trimming a project a second time will offset your In and Out points.*

- 5 Click Create Project.

- 6 When asked, specify the location and name of the new project based on the trimmed clips; make sure it's a different folder than the original location. Click Save.
- 7 Close the original project. Choose File > Open, locate the trimmed version, and click OK.
- 8 Examine the trimmed version of the project. If it's satisfactory, you can delete the original project and its source clips or move them to an archive disk.

Using a Premiere project on another platform

Premiere project files are designed to be usable across computer platforms. You can open and work with a Premiere project on any other platform on which Premiere 6.0 is available.

Transferring a Premiere project to another platform is similar to moving a Premiere project to another computer: You must move not only the project file, but all of the source clips used in the project. In addition, follow these guidelines:

- All of the source files must be in a format supported by the destination platform. For example, if you plan to transfer a project to Mac OS for editing, don't use Windows PCX files. For more information about filename extensions and platform support for various file formats, see "Importing clips" on page 151.
- All files must conform to the destination platform's filename conventions. For best results, use the 8.3 filename convention (eight characters and a three-character filename extension). For example, a Premiere project uses the extension .PPJ.
- For best results, make sure that source clips are saved using cross-platform codecs such as Motion JPEG A or Motion JPEG B, provided by QuickTime.
- Any fonts used in titles must be available on the destination platform.
- When you open the project on the other platform, you'll be asked to locate each source clip (see "Opening a project" on page 85). You might want to remove unused clips (see "Naming, finding, and deleting items" on page 97) or run the Project Trimmer (see "Removing unused frames from source clips" on page 86) so that you don't have to transfer any more clips than necessary.

Many Premiere settings files can be transferred across platforms, including batch capture lists (Windows filename extension: .PBL), batch processing lists (.HBP), edit decision lists (.EDL), exported file lists (.TXT), filmstrip files (.FLM), motion settings (.PMT), project files (.PPJ), project settings (.PRS), storyboards (.PSQ), and titles (.PTL).

Command sets (.PFN) and transition sets (.PFX) files cannot be transferred across platforms.



If you have trouble opening a project file from another platform by double-clicking, try using the File > Open command from within Premiere.

Setting up Premiere's scratch disks

When you edit a project, Premiere processes your changes in RAM. When the available RAM isn't enough, Premiere can use hard disk space as an additional work area. Also, Premiere stores some project information, such as preview files, on your hard disk, using the disk the same way you would use a paper scratch pad. If your system has access to multiple *volumes* (disks or disk partitions), you can specify which one Premiere uses as a *scratch disk* for the different temp files it creates when capturing movies, building video previews, and building audio previews. The scratch disk space Premiere uses increases as a program becomes longer or more complex. For maximum performance, follow these tips:

- Store Premiere and the operating system on one hard disk, and capture video to an additional AV-certified hard disk on which nothing else is stored. Save and store your project on the same hard disk as Premiere (preferably the system disk).
- Specify your fastest hard disk for video preview files and capturing. You can use a slower disk for audio preview files. Ideally, you want your video and audio preview files on different disks to reduce the amount of activity necessary for playback. Two partitions on the same disk do not improve playback—you must use two physically different disks.
- Specify only disks attached to your computer—a hard disk located on a network is usually too slow. Removable media may be acceptable if it is fast enough.

To specify scratch disks:

- 1 Choose Edit > Preferences > Scratch Disks and Device Control.
- 2 For Captured Movies, select or create a new folder where Premiere will store video and audio files when you digitize using Premiere.

- 3 For Video Previews, select or create a new folder where Premiere will store files generated when previewing video clips.
- 4 For Audio Previews, select or create a new folder where Premiere will store files generated when previewing audio clips.
- 5 Click OK.

When generating preview files, Premiere can warn you when a scratch disk you specified is running out of space. You can specify the point at which the warning appears.

To specify the warning level for low disk space:

- 1 Choose Edit > Preferences > General and Still Image.
- 2 For Low Disk Space Warning Level, indicate in kilobytes the amount of unused scratch disk space that will trigger the warning. Click OK.

Correcting mistakes

If you change your mind or make a mistake, Premiere provides several ways to undo your work. You can undo only those actions that alter the video program; for example, you can undo an edit, but you cannot undo scrolling a window.

To correct mistakes:

Do one of the following:

- To undo the most recent change, choose Edit > Undo. You can sequentially undo up to 99 of the most recent changes made to the program in any Premiere window. The 99 levels of undo are shared among all Premiere windows.
- To jump to a specific state of the project within the last 99 changes, select an item in the History palette. See “Using the History palette” on page 104.
- To undo all changes made *since* the last time you saved the project, choose File > Revert.
- To undo changes made *before* the last time you saved a project, try opening a previous version of your project that may be stored in the Project Archive folder. The degree to which you can go back depends on the settings you specified for automatic project archiving and how often you saved. See “Saving and autosaving a project” on page 83.

- To stop a change that Premiere isn't finished processing (for example, when you see a progress bar), press Esc, or press Command-period (Mac OS only)
- To close a dialog box without applying changes, click Cancel.

For both the Undo menu item and the History palette, you can specify the number of steps that can be undone. The default is 15. Specifying more steps increases memory requirements but may not affect performance.

To set the number of undo levels:

- 1 Choose Edit > Preferences > Auto Save and Undo.
- 2 In the History/Undo Levels section, type a number for Levels of Undo (1 to 99) and click OK.
- 3 Exit and restart Premiere. You do not need to restart the computer.

Working with windows in Premiere

Three named windows form the main work area in Premiere:

- The Project window is where you import, organize, and store references to clips. It lists all source clips you import into a project, though you don't have to use every clip you import.
- The Monitor window can include the Source and Program views. Use the Source view to see an individual video clip and the Program view to see the current state of the video program being edited in the Timeline.
- The Timeline window provides a schematic view of your program, including all video, audio, and superimposed video tracks. Changes you make in this window appear in the Program view.

For an introduction to these windows, see, "An Overview of Adobe Premiere." For more information about using and customizing the Project window, see "Using the Monitor window" on page 163 and "Using the Timeline window" on page 171.

Premiere also provides specialized windows for tasks such as capturing video (see “Using the Movie Capture window” on page 125), creating titles (see “Creating and setting up a new title” on page 275), mixing audio (see “Working with the Audio Mixer window” on page 263), and storyboarding (see “Creating a storyboard” on page 203).

When you exit Premiere, the positions of windows and palettes are saved. In addition, you can create and save named window layouts as a workspace. For more information, see “Customizable workspace” on page 67 and “Selecting an editing workspace” on page 169.

Using window and palette menus

In Premiere, most windows and palettes include menus that can be displayed by clicking a button. In addition, all windows also have context menus, the content of which depends on the current task or mode. The commands found in window menus, palette menus, and context menus are specific to individual windows or palettes.

To open window and palette menus:


Click the Menu button (▶) near the upper right corner of the window or palette. Choose a menu item or click outside the menu to close it.

To open window context menus:

Right-click (Windows) or Control-click (Mac OS) in the window. Choose a menu item or click outside the menu to close it.

Using the Project window's bin view

A Project window includes a bin view, which shows the bins that have been added to the project. The bin view appears on the left side of the Project window, and can be resized or hidden. When the bins in the bin view contain other bins, the hierarchical structure appears, much like the graphical view of folders and subfolders in your operating system.



*A. Thumbnail viewer B. Bins C. Clip D. Find E. New Bin
F. Create Item G. Delete Selected Items H. Resize Bin Area
I. Icon View J. Thumbnail View K. List View L. Clip
information M. Project window menu*

To hide or display the bin view:

Choose Hide Bin Area or Show Bin Area from the Project window menu.

To resize the bin view:

Drag the Resize Bin Area button located at the bottom of the Project window until you have the size you want. You cannot make the bin view smaller than the four buttons below it. To make it bigger, you may need to first make the Project window bigger.

To add or delete a container in the bin view:

- To delete one or more bins, select the bin and click the Delete Selected Items button (🗑) at the bottom of the Project window.
- To add a bin, click the New Bin button (📁) at the bottom of the Project window.

To display the contents of a bin in the bin view:

Select the bin. If the bin contains other bins, click the triangle beside the bin icon to display them, and then select the bin you want to view.

Organizing clips using bins

Clips in a project can be arranged in bins (with bins inside of bins, if you like), just as files are arranged in folders on your hard drive. Bins are particularly useful for organizing a complex project containing a large number of clips. You can also save a bin for use in other projects.

To manage clips using a bin:

Do any of the following:

- To create a bin, Choose File > New > Bin or click the New Bin button (📁) in the Project window. Type a name for the bin, and then click OK.
- To move a clip into a bin, drag the clip to the bin icon. If the bin window is open, drag the clip to the bin window. In the same way, you can store a bin inside another bin.
- To view the contents of a bin, select the bin in the Project window.
- To open a bin in its own window, right-click (Windows) or Control-click (Mac OS) the bin, and choose Open Bin in New Window.
- To make a bin available for use in other projects, select the bin and choose Project > Export Bin from Project, or right-click (Windows) or Control-click (Mac OS) the bin and choose Export Bin from Project. Then, type a name, choose a location for the bin, and click Save. Bins created and saved in Windows use the extension .PLB.
- To use a saved bin file in any project, click File > Open, select the bin file (.PLB), and click Open.

Using libraries from earlier versions of Premiere


In previous versions of Premiere, you could create containers called *libraries*, which were used to store clips from one or several projects. A library was stored as a separate file apart from any project. Although Premiere 6.0 doesn't directly support libraries, you can open a library. The library is converted into a bin when you open it in a Premiere 6.0 project. If you want to store a set of clips so that they are available for other projects, simply save the bin that contains the clips. See "Using the Project window's bin view" on page 92.

To import a library:

- 1 Choose File > Open.
- 2 Locate and select the library (.PLB) file, and then click Open.

Customizing a Project or Bin window display

Each clip appears in a Project or Bin window with its filename, file type, and duration. You can customize the kind of information that a Project or Bin window displays, and apply different display options to each individual window.



A. Bin view B. Resize Bin Area button

To change a Project or Bin window view:

Click the Icon View (☐), Thumbnail View (▣), or List View (☰) buttons at the bottom of the window.

To sort items in the Thumbnail View or List View:

Do one of the following:

- Click the column heading by which you want to sort the items.
- To reverse the sort order of column items, click the same column heading again.
- To rearrange columns in List View, drag column headings left or right as needed.
- To resize the Bin column, drag the Resize Bin Area button (◀▶).

To customize Icon View, Thumbnail View, or List View:

1 Choose Window > Window Options > Project Window Options.

2 At the top of the dialog box, choose Icon View, Thumbnail View, or List View. The remaining options depend on which view you choose. Select from these options (if available) and then click OK:

- Select a Size for the icon that will represent each file in the Project or Bin window.
- Select Snap to Grid to make window icons line up according to an invisible grid.
- Select Draw Icons to make icons visible. Deselect this option to prevent icon display and make the Project window display faster.
- Type labels for the four fields that you can define.
- Select a sorting method for items in the window.
- Select the fields you want to display in the List View.

To rearrange a Project or Bin window in the Icon View when icons obscure other icons:

With the Icon View active, choose Clean Up View from the Project window menu.

Viewing clip information in the Project window

At the top of a Project or Bin window is the *thumbnail viewer*, which you can use to preview individual clips. This viewer uses the first frame of a clip as the icon or poster frame; this frame is used when the Project window is set to Icon View or Thumbnail View—it is also used as the sample frame for the Title window (see “Importing a sample frame” on page 275). You can change the poster frame to any frame in the clip.

To view a clip and its information in the Project window:

- 1 Select the clip in the Project window. Premiere displays the clip’s information beside the thumbnail viewer in the upper left corner of the Project window.

Note: The average data rate is displayed for all video clips. This information is useful for analog video because maintaining a consistent data rate for all clips in a project results in smoother playback from the Timeline.

- 2 View the clip by pressing the Play button (▶) on the thumbnail viewer. Press Play again to stop playback.

- 3 Select List View, if necessary, and expand or scroll along the right side of the window to see all of the columns of information.

- 4 Choose Clip > Properties.

To change the poster (icon) frame for a clip:

- 1 Select the clip in a Project window.

- 2 Press the Play button (▶) or drag the play slider on the thumbnail viewer in the upper left corner of the Project window until the frame you want is displayed.

- 3 Click the Set Poster Frame button (🖼️).

Using the Project window’s List View fields

The following fields are available in the List View:

Name By default, displays the clip name on disk. You can change the name the clip uses inside the project. For more information, see “Naming, finding, and deleting items” on page 97.

Date The most recent modification date of the source file.

File Path Location of the file on disk, expressed as a folder path.

Log Comment The text typed in the Comment field when the clip was logged during capture, if it was captured using Premiere.

Media Type The kind of media, such as Movie or Still Image.

Video Info The clip's video characteristics, such as the frame size.

Audio Info The clip's audio characteristics, such as sample rate, sample size, and stereo or mono.

Video Usage The number of times the video component of a clip is used in the Timeline.

Audio Usage The number of times the audio component of a clip is used in the Timeline.

Duration Length of the clip, expressed in the currently specified Time Display option (see "General settings" on page 75).

Timecode The timecode of the first frame, for source video that was captured from tape.

Reel Name The reel name typed in when the clip was logged during batch capture, if it was captured using Premiere.

Notes Displays comments you type in this field. You can change the name of this field.

Labels Additional fields for labels to be used for identification and sorting. You can change the names of these fields.

 *In Icon View, you can arrange the icons by dragging them. If you select and drag multiple icons to the Timeline at once, they will appear in the Timeline in the same order as in the Project Window.*

Naming, finding, and deleting items

Manage the clips and other items in your project using the tools to rename, find, and delete items. All clips in your project (including captured DV clips that automatically appear in the Project window after capturing) exist on your hard disk—only a reference to each clip is added to the Project window in Premiere. Whenever you rename, edit, or delete a clip in Premiere, the original file remains untouched on your hard disk.

To manage project items:

Do any of the following:

- To rename a clip, select the item, choose Clip > Set Clip Name Alias, type the new name, and then click OK. In List View, you can also select the name and type a new one.
- To rename a bin, select the bin name, highlight the old name or backspace over it, and type the new name.
- To view a clip's original name or change its alias, select the item in the Project or Bin window and choose Clip > Set Clip Name Alias. Type a new name or click None to remove the alias.
- To rename an original source file on disk, exit Premiere and rename the file using the Windows Explorer (Windows) or Finder (Mac OS). The next time you open the project that uses the renamed file, Premiere will ask you to locate the file (see "Opening a project" on page 85).
- To delete an item from a Project or Bin window, select the item and press the Delete key.
- To delete all clips in a project that are not currently used in the Timeline, choose Project > Remove Unused Clips (also see "Removing unused frames from source clips" on page 86).

***Note:** Because Premiere stores references to clips and not the originals, deleting a clip from a project or bin removes it from the project and Timeline (if it was included there) but does not delete the corresponding original source clip from your hard disk.*

- To find any item in a project or bin, based on the contents of any column in the Thumbnail View or List View, select the window you want to search and choose Edit > Find. Specify options as needed and click Find. To find an item in the Project window, click the Find button (🔍), specify options, and click Find.

Printing window contents

You can print the contents of the Project, Storyboard, or Timeline windows for use in a storyboard or to document your project. You can also print the File Properties and Data Rate Graph windows or the first frame of the clip in the Clip window.

To print the contents of a window:

- 1 Click the Project, Storyboard, Timeline, Clip, File Properties, or Data Rate Graph window to activate it.
- 2 If necessary, choose File > Page Setup, specify page options, and click OK.
- 3 Choose File > Print, specify printing options and click OK.

Note: *The options in the Page Setup and Print dialog boxes come from the driver software for the currently selected printer, not from Premiere. For information about printing options, see the documentation for your printer software.*



To save paper when printing a wide window, such as the Timeline, choose File > Page Setup and set the paper orientation to Wide or Landscape.

Creating a text list of project files

To document the contents of a project, you can export a text file that lists all the clips used in a project. The list displays the original filenames of clips, bins, and bin contents in the order in which they appear in a Project window. If a Bin window is active when you export, Premiere exports a file list for the project that includes the bin and its contents. In Windows, the file list contains the pathname to the file. In Mac OS, you can choose whether you want to include the full pathname.

To export a file list:

- 1 Activate a Project window.
- 2 Choose File > Export Timeline > File List.
- 3 Specify a location and type a name for the file list.
- 4 (Mac OS only) Select Include Full Path Names if you want to include a complete folder path for each file in the list.
- 5 Click Save.

Changing the startup window

When you start Premiere, it displays the palettes you left open the last time you used Premiere. You can also make the Open, New Project, or Load Settings dialog box appear automatically at startup.

To change the startup window:

- 1 Choose Edit > Preferences > General and Still Image.
- 2 Choose an option from the Window at Startup menu and click OK:
 - None starts Premiere with the palettes from the previous session.
 - New Project opens the New Project dialog box when you start Premiere.
 - Open Dialog opens the Open dialog box when you start Premiere.
 - Load Settings opens the Load Project Settings dialog box when you start Premiere.

Working with palettes

Adobe Premiere includes several palettes that display information and let you modify clips. You can display, hide, or recombine palettes as you work.

Changing the palette display

You can change the arrangement and display of palettes and palette groups to make the best use of space on your monitor.


To show and hide palettes:

Do one of the following:

- To show or hide a palette, choose the name of the palette from the Window menu.
- To hide or display all open palettes, press the Tab key.

To move a palette to another group:

Drag a palette tab to that group.



Drag a palette to another group (left). Palettes are combined (right).

To separate a palette:

Drag a palette tab to another location.

To dock a palette to another palette group:

Drag a palette tab to the bottom of another palette until the bottom of the destination palette is highlighted, and then release the mouse.

To separate a palette from other palettes to which it is grouped or docked:

Drag a palette tab away from the other palettes.


 *If you have more than one monitor connected to your system and your operating system supports a multiple-monitor desktop, you can drag palettes to any monitor.*

Using the Info palette

The Info palette displays information about a selected clip or transition. If you drag a clip in the Timeline, you can watch the starting and ending time change in the Info palette. The information displayed in the palette may vary depending on factors such as the media type and the current window. For instance, an empty space in the Timeline, a rectangle in the Title window, and a clip in the Project window display information unique to each item when selected.

Using the Navigator palette

Use the Navigator palette to quickly change your view of the Timeline by dragging a view box within a miniature representation of the Timeline. You can also change the level of detail displayed in the Timeline.



A. Timecode B. Zoom Out button C. Zoom slider D. Zoom In button E. Current View box F. Edit Line G. current work area

To change the view of time using the Navigator palette:

Do any of the following:

- Double-click the timecode, type a new time, and press Enter (Windows) or Return (Mac OS). The edit line moves to the new time.
- Click the Zoom Out button to make more of the Timeline visible at once.
- Drag the Zoom slider left to reduce or right to magnify the Timeline.
- Click the Zoom In button to magnify the Timeline at the edit line.
- Drag the Current View box to scroll the Timeline.
- Press Shift as you drag the edit line in the Navigator palette to move the edit line in the Timeline.

Using the Commands palette

The Commands palette comes with a list of preset commands, which you can modify to suit your needs. You can create a custom set of buttons for fast access to your favorite menu commands, and assign a function key to each button for instant keyboard access.

To add a command to the palette:

- 1 If the Commands palette is not visible, click its tab or choose Window > Show Commands.
- 2 Choose Button Mode from the palette menu to deselect it.
- 3 Click the Add Command button (□).
- 4 For Name, type the text you want to appear on the button (optional).
- 5 Choose the command for the new button from the Premiere menu bar.
- 6 For Function Key, choose the keyboard shortcut you want for the button (optional). The menu displays keys that are not already assigned to other commands (Windows) or dims keys that are already assigned to other commands (Mac OS).
- 7 For Color, choose a color for the button and click OK.
- 8 Choose Button Mode from the palette menu to select it.

To manage command sets:

Deselect button mode, and then choose any of the following commands from the Commands palette menu:

Play Command Executes the command for the selected button. Select the button you want to play, and click Play Command. You can also execute a command by clicking the Play Command button (▶) at the bottom of the Commands palette.

Add Command Adds a new button to the Commands palette. (See the previous procedure.) You can also add a command by clicking the Add Command button (□) at the bottom of the Commands palette.

Delete Command Removes command buttons. Select the button you want to remove and click Delete. When Button mode is off, you can delete a command by selecting it and clicking the Delete Command button (⊞) at the bottom of the Commands palette.

Command Options Modifies command buttons. Select the button you want to change and select options (as explained in the previous procedure). When Button mode is off, you can change command options by double-clicking a command.

Load Commands Replaces the existing buttons with a set saved on disk.

Save Commands Preserves your commands in a file. This is useful for creating custom command sets for different purposes, such as one for video capture.

Button Mode Turns Button mode on and off. Use Button mode when you want to use buttons in the Commands palette. Turn Button mode off when you want to manage buttons. Button mode is on when the check mark by it is displayed.

Using the History palette

Use the History palette to jump to any state of the project created during the current working session. Each time you apply a change to some part of the project, the new state of that project is added to the palette.

For example, if you add a clip to the Timeline window, apply an effect to it, copy it, and paste it in another track, each of those states is listed separately in the palette. You can select any of these states, and the project will revert to how it looked when the change was applied. You can then modify the project from that state.

The following guidelines can help you with the History palette:

- Program-wide changes, such as changes to palettes, windows, and preferences, are not changes to the project itself, and so are not added to the History palette.
- Once you close and reopen the project, the previous states are no longer available in the history palette.
- When you close a Storyboard window, Title window, or Batch Capture window, states created in those windows are removed from the History palette.
- Applying the Revert command deletes all the states that existed since the last save.
- The oldest state is at the top of the list, and the most recent one is at the bottom.
- Each state is listed with the name of the tool or command used to change the project, as well as an icon representing the tool or command. Some actions generate a state for each window affected by the action. These states are linked and act as a single state.
- Selecting a state dims those below it, to indicate which changes will be removed if you work from the project at that state.
- Selecting a state and then changing the project removes all states that came after the one you selected.

To display the History palette:

Choose Window > Show History.

To display a state of the project:

Click the name of the state in the History palette.

To move around in the History palette, do any of the following:

- Drag the slider or the scroll bar in the palette.
- Choose Step Forward or Step Backward in the History palette menu.

To delete one project state, select the state and do one of the following:

- Choose Delete in the History palette menu.
- Click the Delete button (🗑) and then click Yes.
- Alt-click (Windows) or Option-click (Mac OS) the Delete button (🗑) to avoid the delete warning message.

To clear all states from the History palette:

Choose Clear History in the History palette menu.

Using other palettes

Premiere includes two additional palettes not covered in this chapter. The Transitions palette is described in “Using the Transitions palette” on page 239. The Effect Controls palette is described in “Applying and controlling effects” on page 327.

http://



2



Chapter 2: Capturing and Importing Source Clips

You can import clips from any source—videotapes, motion-picture film, audio, still images—as long as they exist as digital files stored on disk. The topics in this section cover how to import clips and describe requirements for converting other media types before they can be used digitally in your project.

Source material exists in two main forms:

- *Digital* media is stored in a file format that a computer can read and process directly. Many newer cameras and audio recorders can save images and sound in a digital format. All digital-video (DV) camcorders and decks record video and audio in digital format. Digital media stored on tape must be transferred to disk before Premiere can use it in a project. Premiere can capture digital video from tape and save it to disk as clips that you can then add to your project.
- *Analog* media must be *digitized*, or converted to digital form, before a computer can store and process it. Some examples of analog media are motion-picture film, conventional audio tape, and slides. Premiere, in conjunction with a capture card, can digitize analog videotape such as Hi-8 and save it to disk as clips that you can then add to your project.

Although digital media equipment is becoming increasingly common, a great amount of video and audio continues to be recorded and stored using analog equipment. For this reason, you may need to capture analog video and audio as part of your workflow. You can digitize analog video directly into Premiere if you use digitizing hardware to connect an analog video player or camera to your computer. Video-digitizing hardware is built into some personal computers, but usually must be added to a system by installing a compatible hardware capture card. For a list of compatible cards, see the Adobe Premiere Web site (<http://www.adobe.com/premiere>).

Capture checklist

- Connect the DV or analog camcorder or deck to your system. See “Connecting the analog video source” on page 112 or “Connecting the DV video source” on page 112.
- Set up Premiere for capture. See “Digitizing analog video as DV” on page 113 or “Preparing for DV video capture” on page 120.
- (DV only) If you will be using batch capture but you didn’t prestripe your tape with timecode, see “Recording or replacing timecode (DV only)” on page 114.
- Capture video using any of the following methods:
 - To capture video manually, see “Using the Movie Capture window” on page 125.
 - To capture video manually using device control, see “Capturing clips with device control” on page 127.
 - To capture video automatically using device control, see “Batch-capturing video” on page 130.
 - To capture individual frames to create animation, see “Capturing stop-motion animation” on page 139.
- If the timecode on the video you captured isn’t accurate, see “Reading timecode from source video” on page 142.
- Capture additional material using any of the following methods:
 - To capture audio from an analog source, see “Capturing analog audio” on page 144.
 - To import audio from an audio CD or other digital source, see “Importing digital audio” on page 145.
 - To import still images, animation, or sequences, see “Importing clips” on page 151.
 - To import a project, see “Importing another project” on page 156.
- To use placeholders for missing files, see “Using offline files” on page 158.
- To evaluate a clip, see “Analyzing clip properties and data rate” on page 157.

Understanding offline and online editing

Depending on the level of quality you require and the capabilities of your equipment, you can use Premiere for either online or offline editing when working with analog source material. The settings you specify for capture are dictated by whether you will edit the program offline or online.

Note: When you edit DV clips, all editing is online. DV compression makes standard DV manageable on many systems.

About online editing

Online editing is the practice of doing all editing (including the rough cut) on the same clips that will be used to produce the final cut. Previously, online editing had to be done on expensive high-end workstations designed to meet the picture quality and data-processing requirements of broadcast-quality video. Editors with high-end requirements who could not afford a suitable online system had to rent time at a production facility that owned one. As high-end personal computers have become more powerful, online editing has become practical for a wider range of productions such as broadcast television or motion-picture film productions.

For online editing, you'll capture clips once at the highest level of quality your computer and peripherals can handle.

About offline editing

In *offline editing*, you edit video using low-quality clips and produce the final version using high-quality clips on a high-end system. Offline editing was developed to save money by editing in a less expensive facility. Although offline editing can be as simple as writing down time points for scenes while watching them on a VCR, it is increasingly done using personal computers and Premiere.


Offline editing techniques can be useful even if your computer can handle editing at the quality of your final cut. By batch-capturing video using low-quality settings, you can edit faster, using smaller files. When you digitize video for offline editing, you specify settings that emphasize editing speed over picture quality. In most cases you need only enough quality to identify the correct beginning and ending frames for each scene. When you're ready to create the final cut, you can redigitize the video at the final-quality settings. See "Digitizing analog video as DV" on page 113 and "Creating a batch list to redigitize project clips" on page 137.

Once you have completed the offline edit in Premiere, you can create a table of scene sequences called an *edit decision list*, or EDL. You then move the EDL to an *edit controller* on a high-end system, which applies the sequence worked out in Premiere to the original high-quality clips. In this way, the editing work done on the less expensive workstation is used to create the final cut on the more expensive, higher-quality workstation.

If you will be generating an EDL from your edits, be sure that all clips are captured with frame-accurate timecode corresponding exactly to the timecode of the high-quality source video that you will use for the final online edit. If you plan to edit off line using VHS dubs (copies) of the source clips, be sure that in each dub you burn in the timecode—that is, make the timecode visible in a window in the picture. These steps ensure that the EDL you generate is usable when transferred to the online system or edit bay and that your edits will be frame-accurate. See “Reading timecode from source video” on page 142.

Connecting the analog video source

To capture analog video, first connect the camcorder or deck to the capture card installed in your system. Depending on your equipment, you may have more than one format available for transferring video and audio, including component video, composite video, and S-video. Refer to the instructions included with your camcorder and capture card.




A. S-video connection B. Composite video and left-right audio connections

Connecting the DV video source

To capture DV video, your computer must be able to connect to a DV device using IEEE 1394 (FireWire/i.Link). For detailed instructions on connecting your device, see your device documentation. Premiere’s built-in DV support relies on DV support in the operating system. To provide DV support through their operating systems, Microsoft and

Apple requires IEEE 1394 interfaces that are compliant with the OHCI specification. Many computers include OHCI-compliant IEEE 1394 ports on the computer, and almost all current IEEE 1394 cards are OHCI-compliant. IEEE 1394 interfaces that are not supported by the operating system require their own presets, driver software, and Premiere plug-ins for use from within Premiere. If your computer does not have a built-in IEEE 1394 interface, you can purchase a hardware capture card that provides the interface. Check with your computer's documentation for more information.

The first step in capturing DV video is to connect the camcorder or deck to the IEEE 1394 port or card in your system. Plug an IEEE 1394 connector into the DV In/Out port on the camcorder or deck and plug the other end into the IEEE 1394 port on the system's panel or on the card installed in the system.



Connecting to the IEEE 1394 (FireWire/i.Link) port on the computer

Some DV camcorders require a connection to their power adapter to activate the IEEE 1394 port. Other camcorders may go into sleep mode or demo mode if left in the camera mode without tape activity for a period of time. To avoid these problems, connect your camcorder to its power adapter when setting it up for capturing or dubbing video. If the camcorder goes into demo mode with the power adapter connected, turn off this feature using the camcorder's menu system.

Digitizing analog video as DV

If you will be adding analog video to a DV project, you can avoid compatibility problems by digitizing the analog video as if it were DV. There are several ways to do this:

- Use a DV camcorder with an analog video input, dub the analog tape to DV format tape, and then capture from the DV copy.

- If your camera supports *E-E mode*, in which the inputs are electronically connected to the outputs, connect the analog video signal to the analog input port on the DV device and then connect the IEEE 1394 connector to the computer. Set the Input Select on the DV device to the analog input and enable E-E mode in the device's menu. For more information, see the documentation for your camera.
- Use a media converter, such as Sony DVMC-DA1, to digitize the analog video to DV format without using a camcorder.

The methods just described (that digitize the analog signal and send it directly without first recording it) offer the advantage of speed. If you want to use Premiere's batch-capture feature with DV device control, you must dub the analog video to DV tape first so that the DV timecode is recorded on the tape.

Note: Some capture cards support both analog and DV capture.

Recording or replacing timecode (DV only)

In certain circumstances, it is important that the timecode on your tape be free of any gaps. For example, continuous timecode is essential if you will be using Premiere features such as batch capture or the project trimmer, which depend on consistent In points, Out points, and durations. DV cameras are designed to create a continuous timecode track, even if you stop recording and start again. Discontinuities in timecode can occur, however, if you remove the tape from the camera, reinsert it, and resume recording, or if you rewind the tape and begin recording again at the beginning.

You can address the issue of continuous timecode either before or after you shoot, but regardless of which remedy you choose, you must perform it before you capture video from the tape.

Recording continuous timecode as you shoot

If valid timecode is present on the tape at the frame just before where you will begin recording, subsequent recording will pick up and continue that timecode. To ensure you always shoot continuous timecode, practice the following procedures while shooting:

- Before you eject, fast forward, rewind, or play a tape, record 5 seconds of scratch video.
- When you resume recording, cue the end of the tape up to about 1 second into the scratch video.

- Observe the timecode being recorded to verify that you have not created a timecode discontinuity. If the timecode restarted at 00:00:00:00, stop recording, rewind into the scratch video again, and then continue recording.

Recording timecode before shooting

You can also ensure that a tape will have continuous timecode by recording timecode onto the tape before using it. This process is called *striping* the tape. When you stripe a tape, you must be careful not to change the camera's settings before recording; otherwise, you can record discontinuities onto the tape. For example, if you stripe a tape with the camera set to record in 12-bit/32-kHz audio, and then just before you shoot the video you change the camera's audio setting to record at 48 kHz, you may record a sample rate discontinuity onto the tape. Such discontinuities do not capture well and can only be fixed by dubbing the tape with analog connections.

To record timecode onto a tape before shooting:

- 1 Load a tape into your DV camcorder or deck, and make sure that it is fully rewound.
- 2 If you are using a camcorder, completely cover the lens using a lens cap or opaque material.
- 3 Begin recording. Let the camcorder or deck run until the entire tape has been recorded.
- 4 Make sure that your camera's settings remain the same for striping and for shooting.

Replacing timecode

If your tape does not contain continuous timecode, you can create a copy, or *dub*, of the tape and record new timecode onto it. To record new continuous timecode onto the tape, copy the tape without the original timecode. You can then capture video (and the new timecode) from the copy.

To replace the timecode on a tape:

- 1 Load the tape you have shot into a DV camcorder or deck, and make sure that it is fully rewound.
- 2 Set the camcorder to VTR mode.
- 3 Load a new tape into a second camcorder or deck, which you will use to record the copy.

- 4 If the second device includes an option to record video with the timecode from your original tape, be sure that this option is disabled. See the operating instructions for the device for information on this option.
- 5 Connect the two devices using an IEEE 1394 cable.
- 6 Begin recording the new tape and then start your original tape playing. Let the camcorders or decks run until the entire original tape has been copied.

File-size limitations

Premiere's Timeline window can contain up to three hours of video; however, the actual file-size limitation is not determined by Premiere, but by your capture card, operating system, and hard disk. Premiere considers a *large file* as anything larger than 2 GB. Check your capture card and hard disk documentation for information on large file support.

Note: Large analog file capture is not supported in Premiere.

Using large files in Mac OS

To capture, export, import, render, preview, or print to video large files (greater than 2 GB) in Premiere, you need the following:

- Mac OS 9.0.4
- Quicktime 4.1.2 or later
- Mac OS Extended volume format (HFS+)

If one of these three components is missing and you are capturing a large file, Premiere will generate a *referenced movie* instead of one large movie file. A referenced movie is a series of files, each under 1.99 GB, and each referencing the next. These reference files share a common name, for example, Myfile, Myfile01, Myfile02, Myfile03. You can open or import the first file (or the “parent file”) of a referenced movie, and the remaining files (“child” files) open automatically. If you attempt to open a child file, Premiere displays an error message. When you import or open a referenced movie, Premiere interprets it as one large file.

Using large files in Windows

Large (greater than 2 GB) file support for Premiere for Windows varies because of the numerous Windows operating systems and disk formats. When using large files, keep the following in mind:


- To use large files in Premiere for Windows, you need either a FAT 32 or an NTFS-formatted hard disk. If you're using QuickTime-based hardware for capturing, you'll also need QuickTime 4.0 or later.
- To capture large DV files, you need Windows 98 Second Edition, Windows 2000, or Windows Millennium Edition.
- To export a large file to DV tape, you need Windows 98 Second Edition, Windows 2000, or Windows Millennium Edition.
- To import, render, preview, print to video, export movie, or export to analog tape a large file, you need Windows NT, Windows 98 Second Edition, Windows 2000, or Windows Millennium Edition.

Preparing for analog capture

Premiere is sold with many video-capture cards, which usually include non-Premiere software written by the card manufacturer to control the specific card. Most video-capture card software is written so that its controls appear within Premiere for your convenience, even though much of the actual video processing happens in the card, outside of Premiere. This complex relationship between video-capture cards and Premiere can make it difficult to identify which part of the system is responsible for a particular option or problem. Adobe, as well as most capture card manufacturers, provides troubleshooting documents online that can help you determine if an option or problem you are working on belongs to or is caused by the video-capture card and its software, or Premiere. These online documents can also help you resolve technical issues you may encounter while using your capture card and Premiere. See the Adobe Premiere Web site (<http://www.adobe.com/premiere>) for links to troubleshooting resources. If the issue is traced to the video-capture card, see the documentation provided by the manufacturer or the manufacturer's Web site.

Most of the supported capture cards provide a settings file (preset) that you can select in Premiere's Load Project Settings dialog box. This preset automatically sets all capture settings for optimal support with your capture card. If your capture card provides a preset, Adobe recommends that you select it for projects in which you will capture clips or import captured clips, and that you do not change the capture settings in the Settings dialog box.

Most of the settings that control how a clip is captured from a camera or a deck are found in the Capture Settings section of the Project Settings dialog box. Settings vary depending on the selection for Capture Format. Available capture formats vary depending on the type of video-capture card installed. Premiere also provides some capture-related settings in the Scratch Disks and Device Control section of the Preferences dialog box. Open the Capture Settings or Preferences dialog boxes by clicking the appropriate Edit button in the Settings section of the Movie Capture window. (You may need to select Expand Window from the Movie Capture window menu to display the settings.)



Settings vary depending on the selected capture format. Capture Settings for Video for Windows capture are shown. Available capture formats vary depending on the type of video-capture card installed.

To prepare for capturing analog video:

1 Specify the scratch disk for captured movies. See “Setting up Premiere’s scratch disks” on page 88.

Note: *The length of a captured clip may be limited by the file-size limits of your operating system. For more information, see “File-size limitations” on page 116.*

2 Set up the video source. For QuickTime for Mac OS, choose Project > Project Settings > Capture, click Video, choose Source, and choose a video source from the Digitizer menu. For an editing mode provided with a video-capture card, see the documentation included with the video-capture card.

3 Carefully check other settings in the Capture panel (summarized below). As noted in the following list, some capture settings are specific to a particular capture format.

Capture Format Select the file format for your video program. Changing the Capture Format changes the options available in the Capture Settings dialog box as well as in the dialog boxes that appear when you click the Video, Audio, and Advanced buttons.

Capture Video Select to enable video capture.

Size (QuickTime) Type the width and height of the digitized frame in pixels, and select Constrain to restrict the aspect ratio to 4:3. For Video for Windows capture, click Video to specify frame size.

Rate (Video for Windows) If available, choose a frame rate for digitizing video. For NTSC, choose 29.97 fps; for PAL and SECAM, choose 25 fps.

Video, Audio, Advanced, VFW Settings If available, click to set options provided by software that came with your video-capture hardware, usually including compression settings. Understanding these card-specific options is critical for successful capturing; see the documentation for your capture hardware.

Capture Audio Select to enable audio capture. For QuickTime capture, or if these options are not available, click Audio to specify audio settings. For Video for Windows capture, specify settings for Rate (the sample rate for digitizing audio used by your capture device), Format (the bit depth of digitized audio used by your capture device), and Type (the compression method for digitized audio). If you chose an Editing Mode other than QuickTime or Video for Windows, and Capture Audio settings are not available, they may be set by the software that came with your audio-capture hardware; click Audio or Advanced to specify audio settings. See “Capturing analog audio” on page 144 and the documentation for your capture hardware.

Report Dropped Frames Select if you want Premiere to display a Get Properties window at the end of capture warning you that one or more frames were dropped.

Abort on Dropped Frames Select if you want Premiere to stop capturing automatically when at least one frame is lost as a clip is being digitized.

Capture Limit Select and type a time span (in seconds) to limit how much video you will allow Premiere to capture in a single capture session. See “File-size limitations” on page 116.

Preroll Time When capturing with device control, specify how far before the In point Premiere winds the tape before capture. The appropriate value varies depending on the kind of deck or camera you are using; see the documentation for your deck or camera.

Timecode Offset When capturing with device control, type the number of quarter frames to adjust the timecode stamped on the captured video so that it corresponds to the correct frame on the original tape. See “Reading timecode from source video” on page 142.

Log Using Reel Name When capturing with device control, select to use the reel name you specified in the Batch Capture list. For information about batch capturing, see “Specifying batch-list settings” on page 135.

 *To help determine the effect of your compression settings on the data rate of the captured video, use Premiere’s Data Rate graph, as explained in “Analyzing clip properties and data rate” on page 157.*

Preparing for DV video capture

Capturing DV video differs from capturing analog video in several ways. Because the DV image is converted directly to digital format in the camcorder, it is ready to be stored on a hard disk and doesn’t need to be digitized in the computer. Therefore, DV input doesn’t need to be captured in the sense that analog video does; it merely needs to be transferred to your computer. To transfer DV in Windows or Mac OS, you need a capture card or computer with an OHCI-compliant interface.

Your computer also needs a DV codec, which is provided in software as part of the operating system, or as a hardware chip on some capture cards. Premiere includes support for DV codecs and can read digital source video without further conversion. You can help prevent dropped frames by using a hard disk capable of sustaining the 3.6-MB-per-second data rate of digital video.

A critical difference between analog capture and digital capture is how you set up Premiere before you begin. Before capturing DV, create a new project, and in the Load Project Settings dialog box, be sure to choose the appropriate DV preset.

***Note:** If the video you are capturing was shot in 16:9 format using an anamorphic lens, be sure to choose a Widescreen (cinema) DV preset. You'll also need to set the pixel aspect ratio for each individual clip after importing. If you don't, Premiere will treat the video as if it were in 4:3 format, resulting in distortion of the aspect ratio.*

To prepare for capturing DV video:

- 1** Connect the DV device (camcorder or deck) to your computer using an IEEE 1394 connection. The connection point on your DV device may be marked DV IN/OUT or IEEE 1394.
- 2** Turn the DV camcorder on and set it to VTR mode (not Camera mode). Setting your camcorder to Camera mode or turning it off may interrupt audio and video routing.
- 3** Start Premiere. When the Load Project Settings dialog box appears, select the desired DV preset from the Available Project Settings list. Select your preset based on the standard format (NTSC or PAL) and the audio rate (32 kHz or 48 kHz) used when you shot your video footage. If you are not sure, check your DV camcorder documentation. DV audio is usually 16-bit Stereo. Click OK.

***Note:** When you set up your project using a default DV preset or the preset supplied by your camera or DV capture card, do not change presets or any settings in the Capture panel of the Project Settings dialog box. All settings are determined by the preset.*

- 4** After the project opens, choose Project > Project Settings > General. Click Playback Settings. When you select a DV preset, the Editing Mode automatically is set to DV Playback (Windows) or QuickTime (Mac OS), both of which provide additional DV playback settings.

- 5** Select from the following settings and then click OK:

Playback on DV Camcorder/VCR (Windows only) Plays back all DV-compressed clips to your video (NTSC/PAL) monitor or the LCD screen on your camcorder.

Playback on Desktop (Windows only) Plays back all DV-compressed clips in the Monitor window or Clip window on your desktop.

Output Device (Mac OS only) Select an option on which to play back all DV-compressed clips: to your video (NTSC/PAL) monitor, or to the Monitor window or Clip window on your desktop.

Output Mode (Mac OS only) Reflects your Output Device selection. If FireWire is set, you can choose between NTSC and PAL modes. The Frame Size and Frame Rate for the selected mode automatically appear below.

Play Audio on Output Device Only (Mac OS only) Select to play audio through the selected output device. If FireWire is selected, audio plays through the FireWire device; if Desktop is selected, audio plays out of the computer. If you don't select this option, audio plays out of the computer. Scrubbed audio *always* plays out of the computer.

Note: Audio and video may not be synchronized if played back through different devices.

Sample Rate (Mac OS only) Select the sample rate used by your DV camera. If you chose the correct preset, this should already be set correctly. Most DV cameras use a sample rate of 32 kHz or 48 kHz; however 44.1 kHz is an available option for some cameras. If your camera uses 44.1 kHz, you can select that here. For best results, your playback format should match your project's settings. See your DV camera's documentation for supported audio settings.

Note: Always capture and edit using the same audio sample rates that your DV camera supports. Do not mix audio sample rates on the same tape, and avoid mixing them in the same project.

Play Also on Desktop When Playing to the Output Device (Mac OS only) Select this option to enable desktop overlay so that DV-compressed clips play to both the output device selected (if other than desktop) and the desktop. When this is not selected, Premiere displays only the first frame of the video clip on the desktop. Leave this option unselected when recording back to DV. When it is unselected, this option saves CPU cycles by not simultaneously outputting to two devices.

Note: When this option is deselected, scrubbing playback still appears on both the desktop and the NTSC/PAL video monitor.

Render Scrub to Output Device Select this option to display rendered frames on the selected output device when you render-scrub the Timeline. To render-scrub, press Alt (Windows) or Option (Mac OS) as you drag the cursor through the time ruler in the Timeline.

High-Quality Playback and High-Quality Scrubbing (Mac OS only) Leave these deselected for faster playback or scrubbing and less impact on the CPU. These options are not selected by default to achieve better performance for all systems.

Deinterlace Desktop Playback (Mac OS only) Select this option if you want Premiere to deinterlace the video before displaying it in the Clip or Monitor window. Selecting this option makes the video appear less blurry when previewing at a larger size. This option has no effect on rendering or final output to the DV device. Deselect this option if your Clip or Monitor window is full size and you want to see all of the video data in the window on your desktop.

Show Marker Comments (Mac OS only) Select this option to display marker comments in the Monitor window on the desktop. See “Using Timeline markers for comments” on page 187.

6 If your DV camera supports and records audio at 44.1 kHz, and your project is set to 44.1 kHz, select Audio Settings from the General Settings menu and then select 44100 Hz from the Rate menu.

7 Click OK to close the Project Settings dialog box.

8 Choose Edit > Preferences > Scratch Disks and Device Control. See the Adobe Premiere Web site (<http://www.adobe.com/premiere>) for a list of supported devices.

9 Select DV Device Control for Device and click Options. Select your camera model. If your particular camera is not listed, see the Adobe Premiere Web site (<http://www.adobe.com/premiere>) to see if a profile for your camera has been recently added.

10 In the Device Control Options dialog box, check the Check Status option. If the status is Offline, Premiere does not see your device and you need to check all your connections and settings; if the status is Detected, Premiere sees your device but cannot control the tape (possibly there is no tape inserted); if the status is Online, Premiere sees your device and can control the tape.

11 Specify the scratch disk for captured movies. See “Setting up Premiere’s scratch disks” on page 88.

Note: *The length of a captured clip may be limited by the file-size limits of your operating system; see “File-size limitations” on page 116.*

Avoiding DV capture problems


If you run into problem while capturing DV videos, refer to this user guide or the documentation for your capture card, camera, or deck, or check the Adobe Web site (<http://www.adobe.com>) for technical support. The following are common issues and solutions that may arise when capturing DV video:

- If your device (camera or deck) goes into sleep mode, close and then reopen the Movie Capture window; or close the Movie Capture window, turn the device off and back on, and then reopen the Movie Capture window. You can disable sleep mode on most cameras by plugging them into the wall outlet and ejecting the tape.
- If captured DV video looks grainy in the Movie Capture window, attach an NTSC or PAL video monitor to the camera and view captured video on it. When capturing, Premiere displays DV video at low quality on the computer monitor to increase decompression speed. The video is actually captured and stored at full quality and always plays at full quality on an NTSC or PAL monitor.
- If the video image does not appear in the Movie Capture window, verify your device control and capture settings. To access device control settings from the Movie Capture window, click Edit under Device Control, and then click Options in the Preferences dialog box. In the Device Control Options dialog box, make sure that the Check Status option is set to Online. If it is not set to Online, make sure that the options are set correctly, that your device is on and set correctly, and that your IEEE 1394 connections are secure. To ensure that Premiere can see the device, quit Premiere, leaving the device on, and then restart Premiere. Then open the Movie Capture window, click Play (▶), and click within the capture preview area.
- If the video image is offset in the Movie Capture window, try resizing the window to redraw the image.
- If captured audio and video are not in sync, make sure that your audio settings match the device settings and the settings you used to record onto the tape. Also, make sure that you did not record any blank sections of tape. Blank areas in a tape may cause interruptions in the camera time mode, so when you capture the blank area, the camera doesn't transmit valid frames, but QuickTime or Video for Windows is still marking time. To ensure proper timecode recording, see "Recording or replacing timecode (DV only)" on page 114.

Using the Movie Capture window

Use the Movie Capture window to capture DV and analog video and audio. This window includes a preview window, which displays your currently recording video, controls for recording with and without device control, a Settings panel for viewing and editing your current capture settings, and a logging panel for entering batch capture settings. You can log clips for batch capture only when using device control. You can set the preview area to the Fit in Window mode so that the video always fills the preview area.

Note: When performing anything other than capturing in Premiere, close the Movie Capture Window. Because the Movie Capture window assumes primary focus when open, leaving it open while editing or previewing video disables output to the DV device and may decrease performance.



A. Preview area B. Logging panel C. Settings panel D. Movie Capture window menu E. Controllers


The Movie Capture window menu displays options depending on the capture format you are using. For example, the QuickTime capture format includes the Video Input, Audio Input, and Advanced menu options, whereas the Video for Windows capture format does not. Use the Movie Capture window menu to customize the Movie Capture window in the following ways:

- To change the capture settings, choose Capture Settings, select your options in the Capture Settings dialog box, and click OK.

- In Mac OS only, to change Video Input, Audio Input, or Advanced capture settings, select the appropriate option, change your settings, and click OK.
- To remove the tabbed controls from the right side of the window, choose Collapse Window.
- To display the tabbed controls, choose Expand Window.
- To change the size and aspect ratio of the image so that it fills the image area, choose Fit Image in Window to select it. (Certain capture cards do not support playback at full size. When you use one of these cards, Fit Image in Window is not available.)
- To maintain the original size and aspect ratio of the image, choose Fit Image in Window to deselect it.

Capturing clips without device control

If you don't have a controllable playback device, you can capture video from analog or DV camcorders or decks using the Movie Capture window. While watching the picture in the Movie Capture window, manually operate the deck and Premiere controls to record the frames you want. For example, you can use this method to capture video being played from an inexpensive consumer VCR or camcorder.



A. Take Video B. Take Audio C. Record

To capture a clip without a controllable device:


- 1 Make sure that the deck or camcorder is properly connected to your computer.
- 2 Choose File > Capture > Movie Capture.
- 3 Use the controls on the deck or camcorder to move the videotape to a point several seconds before the point where you want to begin capturing. Be sure to leave enough time for the deck to reach the proper speed.

- 4 Press the Play button on the deck or camcorder, and then click Record in the Movie Capture window.
- 5 When you see the point where you want to stop recording, wait a few seconds to provide room for editing, and then click the mouse or press the Escape (Esc) key to stop recording.
- 6 When the Save File dialog box appears, specify a location and filename, and click Save. If you have a project open, the captured clip appears in the Project window.

Capturing clips with device control

Device control refers to control of the video deck or camera from within Premiere when capturing clips. You can use it to capture video from analog or digital video decks or cameras. Premiere includes built-in support for DV device control. With device control, you can do the following:

- Control the device and view its source video directly from Premiere instead of switching between Premiere and the device controls.
- Use the Movie Capture or Batch Capture windows to create a list of *In points* (starting timecode) and *Out points* (ending timecode) for each clip, and then record all clips in the list automatically.
- Capture the timecode on the tape so that Premiere uses it during editing.



A. Previous Frame B. Next Frame C. Stop D. Play E. Play Slowly in Reverse F. Play Slowly G. preview area H. jog control I. shuttle control J. Take Video K. Take Audio L. Rewind M. Fast Forward N. Pause O. Record P. Set In Q. Set Out R. Timecode S. Capture In to Out

Use this checklist to prepare for capturing with device control:

- Make sure that you have the necessary equipment. You'll need a frame-accurate tape deck or camera that supports external device control, a cable that connects the deck to your computer, a Premiere-compatible plug-in software module that lets you control the device directly from Premiere, and source videotape recorded with timecode. Most DV devices meet this requirement using Premiere's built-in DV device control.
- Set the general device control options for capturing as explained in the previous section.
- Use the following procedures to configure Premiere to recognize the device, set capturing options, and capture the video.

***Note:** The capabilities of device control vary depending on the brand and model of playback device you are controlling. For information, see the documentation that came with the device or with its device-control software.*

To specify the capturing device and its options:

1 Display the Scratch Disks and Device Control Preferences dialog box by doing one of the following:

- Choose Edit > Preferences > Scratch Disks and Device Control.
- In the Movie Capture window, click the Settings tab and then click Edit under Preferences.

2 In the Device Control section, select a device, such as DV Device Control, from the menu. Many devices come with a Premiere-compatible plug-in that displays the name of the device in this menu when the plug-in is installed correctly.

3 Click Options, select the appropriate options, and click OK.

***Note:** If your device plug-in includes a Device Model option, be sure to choose the complete model number of the camcorder or deck. This model number is the longer of several model numbers that may appear on the device, and can usually be found on the bottom of the camcorder or the back of the deck.*

4 Click OK to close the Preferences dialog box.

To capture a clip using device control:

1 Choose File > Capture > Movie Capture.

2 If Device Control has not been set up, click Enable Device Control and then see the previous procedure, "To specify the capturing device and its options."

- 3** Test the device control buttons to verify that they work and that you see video in the preview window.
- 4** Type the reel name from the tape in the Reel Name box. (You may be asked to specify the Reel Name each time you insert a new tape, depending on the device control software and the video deck or camera.)
- 5** Use the controls in the Movie Capture window to move to the place in the videotape where you want to start capturing the clip, and click the Set In button (⏪).
- 6** Use the controls in the Movie Capture window to move to the place in the videotape where you want to stop capturing, and click the Set Out button (⏩).
- 7** To move or play in relation to the In and Out points you have set, do either of the following:
 - To move the tape to the In point, Alt-click (Windows) or Option-click (Mac OS) the Set In button (⏪).
 - To move the tape to the Out point, Alt-click (Windows) or Option-click (Mac OS) the Set Out button (⏩).
- 8** Use the controls in the Capture window to do any of the following:
 - Drag the jog control (⏮) one pixel to the left or right to rewind or advance the tape one frame.
 - Drag the shuttle control (⏭) to change the speed of the tape based on the distance of the control from the center point. Depending on your device, you can move the tape from four to 15 speeds in each direction.
 - Press the Previous Frame button (⏮) to reverse the tape one frame. If the device is not playing, Premiere starts it and rewinds one frame.
 - Press the Next Frame button (⏭) to move forward one frame. If the device is not playing, Premiere starts it and moves the tape forward one frame.
 - Press the Stop button (■) to stop playing the tape.
 - Press the Play (▶), Play Slowly (⏪), or Play Slowly in Reverse (⏮) buttons to play the tape accordingly.
 - Press the Rewind button (⏮) to rewind the tape. If you rewind when the tape is stopped, the device rewinds at full speed. If you rewind when the tape is playing or paused, the device rewinds as fast as it can while still displaying video in the Capture window. You can also press the J key on your keyboard to move the tape in reverse at double speed.

- Press the Fast Forward button (⏩) to fast-forward the tape. If you fast-forward when the tape is stopped, the device moves the tape forward at full speed. If you fast-forward when the tape is playing or paused, the device moves the tape forward as fast as it can while still displaying video in the Capture window. You can also press the L key on your keyboard to move the tape forward at double speed.

9 To record the tape, do any of the following:

- Press the Record button (●) to record a clip from the current input video stream.
- Alt-click (Windows) or Option-click (Mac OS) the Record button (●), or click Capture In/Out. Premiere automatically moves the tape to the Preroll specified before the In point, plays the tape, begins capturing at the In point, and stops capturing at the Out point. If you've typed a name in the Logging panel, the new clip will be given that name.

10 After Premiere completes the capture, the Save File dialog box appears. Specify a location and filename, and click Save. If you have a project open, the captured clip appears in the Project window.

Batch-capturing video

If you have the proper setup for device control and have a videotape recorded with timecode, you can set up Premiere for automatic, unattended capture of multiple clips from the same tape. This is called *batch capturing*. You *log*, or create a list of, the segments you want to capture from the tape in the Batch Capture window. The list (called a *batch list* or *timecode log*) can be created either by logging clips visually using device control or by typing In and Out points manually. When the batch list is ready, click one button to capture the clips in the list. You can batch-capture clips from analog or DV camcorders or decks.

Note: Batch capture is not recommended for the first and last 30 seconds of your tape because of possible timecode and seeking issues. Instead, capture these sections manually.



A. check-mark column B. Sort by In Point button C. Capture button D. Add New Item button
E. Delete Selected button

The check-mark column at the far left of the Batch List window shows the status of a clip. If the column has no icon, the clip has not been captured and is not set to be captured. A diamond (◆) indicates that this clip will be captured when you click Capture (●). Click in the column to turn the diamond on or off. A check mark (✓) indicates that this clip has been captured. An X (✗) indicates that an error occurred while capturing a clip.

When you click Capture (●), Premiere scans the list of files and checks your hard disk for other files with the same name. If a duplicate exists, Premiere adds the duplicate icon (Ⓝ) next to the filename in the Batch Capture window. You can then choose to replace the existing files on disk with the new files you're about to capture, or you can rename the files in your batch list.

In the Batch List window, click Add (Ⓝ) to create a new batch list entry, or click Delete (Ⓞ) to remove a selected entry. Double-click a clip to edit its capture parameters, such as filename or reel name. You can sort batch list entries according to their timecode In points by clicking Sort (≡). When you begin capture, Premiere automatically resorts entries by reel name and timecode In points.


Logging clips to a batch list

Specify which scenes you want to use from the source tapes by *logging* scenes—typing the beginning and ending times—in a batch list. If you have set up device control in the Preferences dialog box to remotely control your camera or deck, you can create a batch list of clips automatically by using the clip-logging controls in Premiere, and then use Premiere to capture all the clips in the list automatically. You control tape playback from within Premiere and mark scenes as you see them. This is the easiest and most efficient method.

There may be times when you plan to capture video using a deck controlled by Premiere, but you don't have continuous access to the computer connected to that deck. This can happen because device-controllable decks are more expensive than decks without device control. For example, you may be using a device-controllable deck in an editing suite where you rent time, or many editors might have to share a device-controllable deck in a company or school. In these cases you can log clips manually, using equipment as simple as a home VCR, a copy of the source tape with burned-in (visible) timecode, and a sheet of paper. With this method, you log frame numbers by hand and later type the log manually into the Premiere batch list for use during the capture session with the device-controllable deck.

To add batch-list entries using device control:

- 1 Make sure that device control settings are correctly specified. See “Capturing clips with device control” on page 127.
- 2 Choose File > Capture > Movie Capture.



3 Click the Logging tab, and type the reel name used for the video tape. (You may be asked to specify the Reel Name each time you insert a new tape, depending on the device control software and the video deck.)

4 Use the controls in the Movie Capture dialog box to move to the place in the videotape where you want to start capturing the clip, and click Mark In (⏪). Depending on the device, you cannot capture from the first 4 to 10 seconds of a DV tape.

***Note:** When setting In and Out points in the Movie Capture window, you can use either the Mark In (⏪) and Mark Out (⏩) buttons in the controls below the image, or the Set In and Set Out buttons in the Logging section. See also the Premiere Quick Reference Card for keyboard shortcuts that can trim time from this process.*

5 Use the controls in the Movie Capture dialog box to move to the place in the videotape where you want to stop capturing, and click Mark Out (⏩).

6 Click Log In/Out. Then type a new filename if you don't want to use the default name, type any comments you want to add, and click OK.

7 Repeat steps 4 through 6 for each clip that you want to capture from this reel.

8 Close the Movie Capture window.

9 If you have another tape that you want to capture, insert it, update the reel name in the Batch Capture window, and repeat steps 2 through 8.

10 Make sure that the Batch Capture window is active and choose File > Save. If necessary, specify a location and a filename, and then click OK.

To add batch-list entries manually:

1 Open a new or existing batch list by doing one of the following:

- To create a new batch list, choose File > Capture > Batch Capture. Then choose File > Save As. Specify a location, type a name, and click Save.
- To open an existing batch list, choose File > Open, select the batch list file, and click Open.

2 Click Add New Item (☰), and specify the following options:

- For Reel Name, type the name of the reel, or tape, from which you are capturing the clip.
- For File Name, type a name for the video file that the capture will create.
- For Comment, type any other information you want to provide about the clip.

- For In Time, type the In point timecode for the clip. If you substitute periods for colons or type numbers without punctuation, the display to the right of this option tells you how Premiere interprets the numbers you type as hours, minutes, seconds, and frames.
 - For Out Time, type the Out point timecode for the clip.
 - For Frame Rate, select the frame rate of the source timecode on the tape.
 - For Format, select Drop Frame or Non Drop-Frame. This option is available only if you selected 30 fps from the Frame Rate menu.
- 3 Click OK, and then choose File > Save.
 - 4 Repeat steps 2 and 3 for each of the entries in your timecode log.

Saving, exporting, and importing batch lists

You can save a batch list to disk. In addition, you can export and import a batch list as a text file. You can control the order of the columns in the text file. Saving a batch list and exporting it creates two very different files:

- *Saving* a batch list preserves each entry and its capture settings (described in the next section) in a file format that only Premiere can read.
- *Exporting* a batch list creates a tab-delimited ASCII text file that lists each entry but does not retain the capture settings. You may want to export a batch list as a text file to edit it in text-editing programs or in video-editing systems that can read text batch lists.

The Batch Capture window menu contains commands you can use to manage settings for a batch list.

To save a batch list:

- 1 Activate the Batch Capture window that you want to save and do one of the following:
 - For a new file, choose File > Save As. Specify a location and filename, and click Save.
 - For an existing file, choose File > Save.

To export a batch list as a timecode-log text file:

- 1 Activate the Batch Capture window that you want to export.
- 2 In the Batch Capture window menu, choose Import/Export Settings.

- 3 Drag columns to rearrange them if desired, and click OK.
- 4 In the Batch Capture window menu, choose Export to Text File. Specify a location and filename, and click Save.

To import a batch-list timecode log:

- 1 Activate the Batch Capture window that is to be the destination for the list.
- 2 In the Batch Capture window menu, choose Import from Text File. Locate and select the file, and click Open.

 *After you've logged a tape with comments, you can save the batch list to a disk and store the disk with the videotape. This makes it easy to redigitize clips from that tape in the future.*

Moving batch-list entries between lists:

- 1 Open two or more batch capture windows simultaneously by doing any of the following:
 - Choose File > Capture > Batch Capture to open a new Batch Capture window.
 - Choose File > Open to open an existing batch-list text file.
- 2 Drag a file from one list to another.

Specifying batch-list settings

By default, the settings Premiere uses to capture clips in a batch list are the settings used by the project that is open at the time you log the clips into the batch list. If you want to change the settings, use the Capture Settings (Windows) or Recording Settings, Video Input, Audio Input, or Advanced options (Mac OS) in the Batch Capture window menu. Changes you make using the Recording Settings option are applied to all of the clips in the list unless you attach a settings file to an individual clip. Using different settings for individual batch-list entries requires that you save different settings files. See “Saving and loading project settings” on page 82.

You can also specify *handles* (extra frames to be captured before the In point and after the Out point of each clip) and select a batch-list entry to view in the Movie Capture window for individual capture.

You can modify settings for batch-list entries in the following ways:

- To attach a settings file to an individual batch-list entry, select the entry and choose Attach Settings from the Batch Capture window menu. Locate and select the settings file you want to use, and click Open.
- To remove a settings file from an individual batch-list entry, select the entry and choose Remove Settings from the Batch Capture window menu.
- To specify extra frames to be captured at the ends of each batch-list entry, choose Handles from the Batch Capture window menu. Type the number of frames of additional video that you want to capture before the In point and after the Out point of the clip, and click OK.

Capturing video from a batch list

When you finish building the batch list, you are ready to capture the video. Unless you attach a specific capture settings file to one or more entries, Premiere captures the entries in a batch list using the settings for recording, compression, video input, and audio input that were specified when the clips were logged. See “Specifying batch-list settings” on page 135.

To begin capturing video:

In a Batch Capture window, do one of the following:

- To capture one or more clips directly from the Batch Capture window, first make sure that each clip you want to capture is marked with a diamond (◆) in the check-mark column at the far left of the Batch Capture window; if necessary, click the check-mark column for an entry to turn on the diamond icon, or click the column heading to turn all the entries on or off. Click the Capture button (●).
- To capture a single batch-list entry in the Movie Capture window, select the entry, choose Send In/Out to Movie Capture in the Batch Capture window menu, and click the Capture button (●).

After the batch capture is complete, you can import the captured files into your project using the File > Import command.

To cancel a batch capture:

While a clip is being captured, press the Escape (Esc) key, click the mouse, or press Command+period (Mac OS only).

***Note:** If you attempt to cancel a batch capture while the device is seeking or shuttling to the next timecode, the capture will not cancel and Premiere may return an error. Wait until the device is done seeking or shuttling and then cancel the batch capture.*

Creating a batch list to redigitize project clips

You can redigitize the clips in an existing project using batch capture, and the clips can be logged automatically according to the In and Out points you used in the Timeline. This is helpful when you originally used low-resolution clips for faster editing and are ready to digitize the clips again at high resolution for the final version. By recapturing only the essential segments from the original source reels, you keep file sizes to a minimum. The following procedure does not replace the clips in the current project, but creates a new project.

***Note:** If you know you will be redigitizing clips, be sure to capture the original clips with timecode using device control. This ensures that the clips will have reel names and valid timecode. Premiere cannot use a batch list to digitize clips if no timecode is specified in the batch list or if timecode is not available from the source videotape.*

To prepare a batch list for automatic redigitizing:

- 1 With a project open, choose Project > Utilities > Project Trimmer.
- 2 Select Create Trimmed Batch List, and deselect Copy Trimmed Source Files.
- 3 For Keep _ Frame Handles, type the number of frames you want to capture before the In point and after the Out point of each clip. Specify just enough frames to give you flexibility in fine-tuning edits.
- 4 Click Create Project.
- 5 When asked, specify the location and name of the new project based on the trimmed clips, and then click Save.
- 6 When asked, specify the location and name of the batch-list file that you are creating, and then click Save.
- 7 Make sure that the deck and source videotape are set up properly for capture, and click Capture in the Batch Capture window that appears.

To redigitize project clips manually:

- 1** If the clips you want to recapture are already on your hard disk, close the project and delete or move (Windows only) the clips.
- 2** Open the project, and when the Locate File dialog box opens, select Offline All (Windows) or All Offline (Mac OS).
- 3** If you have customized your project settings after starting the project, choose Project > Project Settings > General, click Save, and then name and save the project settings as a preset file.
- 4** Choose File > Capture > Batch Capture to open the Batch Capture window.
- 5** In the Project window, select all the clips you want to redigitize, and drag them to the Batch Capture window. Repeat for each bin containing clips you want to redigitize.
- 6** In the Batch Capture window, select all the clips, and then choose Attach Settings from the Batch Capture window menu.
- 7** In the Open dialog box, locate the preset settings file used for the project (see step 3) and click Open. (By default, preset files are located in the Premiere 6.0\Settings folder.)
- 8** With the Batch Capture window active, choose File > Save; type a name for the batch list and click Save.
- 9** Close the project. (If you don't close the project, recaptured clips will be imported into the project as new clips instead of replacement clips.)
- 10** Verify that the deck and source videotape are set up properly for capture, and then click the Capture button (●) in the Batch Capture window.
- 11** In the Locate File dialog box that appears, either select an existing bin and click Open, or click New, type a filename, and click Save. This bin is used to collect your captured clips.
- 12** Premiere automatically begins capturing the batch list. To cancel the capture, press the Escape (Esc) key one or more times as necessary.
- 13** When the batch capture is complete, open the project.
- 14** In the Locate File dialog box, locate and select the newly captured clips from the Captured Movies scratch disk (see "Setting up Premiere's scratch disks" on page 88).
- 15** After all of the clips are open in the project, choose File > Save.

Capturing stop-motion animation

Use the Stop Motion feature to perform manual and time-lapse single-frame video captures from a connected camera or from a videotape in a deck or camcorder. For example, you can point a camera at an unfinished building and use the time-lapse feature to capture frames periodically as the building is completed. You can use the stop-motion feature with a camera to create clay animations or to capture a single frame and save it as a still image. In Premiere, stop motion does not require device control. You can capture stop-motion animation from analog or DV sources.



Any movie frame can be used as a visual guide for positioning during stop-motion capturing. The procedure for setting up a background image is the same for the Stop Motion window as it is for the Title window; see “Importing a sample frame” on page 275.

When preparing for stop-motion animation, use the following tips for a more successful capture:

- Turn off the automatic adjustment features in your camera and adjust any settings manually instead. Gradual fluctuations caused by auto exposure or auto focus become sudden changes, which are very apparent in the finished video.
- Plug the camera into the AC power adapter and eject the tape to prevent the camera from going into sleep mode partway through the animation.
- If possible, turn off the demo mode. Demo mode (not available on all cameras) turns on after a period of time when no tape is inserted and the camera is in camera mode or idle mode.

To capture stop-motion animation:

- 1 Choose File > Capture > Stop Motion.
- 2 In the Stop Motion window menu, choose Stop Motion > Capture Options (Windows) or Stop Motion > Recording Settings (Mac OS).
- 3 Do one of the following depending on your platform:
 - In Windows, choose a Capture Type based on whether you want to capture a single frame (Still Image), control stop motion by clicking Capture in the Stop motion window (Manual Capture), or capture stop-motion frames at regular time intervals (Time Lapse).

- In Mac OS, select Manual Recording to control stop motion by clicking a button in the Stop Motion window, or select Time Lapse to capture stop-motion frames at regular time intervals.

Note: Depending on the type of capture you choose, some of the settings described below will be unavailable.

4 Do one of the following, depending on your platform:

- In Windows, type the horizontal and vertical dimensions of the frames to capture in the Size _x_ box. Select Constrain to adjust the values to the aspect ratio used by your capture hardware.
- In Mac OS, select Record at Current Size to capture frames at the dimensions currently displayed in the Stop Motion window, or select Record At and type the horizontal and vertical dimensions of the frames to capture, in pixels. Select 4:3 to maintain a 4:3 frame aspect ratio as you type the values for this option.

5 In Windows only, type a value for Final Movie Will Play Back _ fps to set the frame rate for the captured video.

6 If you selected Time Lapse, type a time value and select a time unit for Capture _ Frames per _ (Windows) or _ Frames per _ (Mac OS). In Windows only, you can also limit the number of frames captured by selecting Capture Limit and typing a number of frames.

7 For Minimum Disk Free Space _ K (Windows) or Stop When Disk Space Falls Below _ K (Mac OS), type a value that specifies how low available disk space can fall before Premiere automatically halts stop-motion capture. The disk monitored for this value is the disk specified in the Captured Movies menu when you choose Preferences > Scratch Disk and Device Control.

8 In Windows only, click the buttons in the upper right corner of the dialog box (if available) to set options provided by software that came with your video-capture hardware. These same settings are accessible from the Capture Settings panel of the Project Settings dialog box (see “Digitizing analog video as DV” on page 113). You can also choose these options from the Stop Motion menu on the menu bar.

9 In Mac OS only, select Stabilize Image Jitters to minimize unstable video signals from some devices.

 To create a still image, you can also capture video as usual and then choose File > Export > Frame. For more information, see “Exporting a filmstrip file for editing in Adobe Photoshop” on page 349.

10 Click OK. Start your camera, tape deck, or other video source, and in the Stop Motion window click Start.

11 Do one of the following:

- If you previously selected Manual Capture (Windows) or Manual Recording (Mac OS), click Start to begin and then click Step every time you want to capture a new frame. You can also press a number on the keypad to capture the specified number of consecutive frames, or press Delete to remove the most recently captured frame.
- If you previously selected Time Lapse, click Start. Premiere captures frames at the specified rate. Click Stop when you want to stop capturing.
- (Windows only) If you previously selected Still Image, wait until your video source displays the frame you want, and click Capture.

12 Choose Save As, specify a location and name for the clip, and click OK.

To manage stop-motion animation (Mac OS only):

Do any of the following:


- To capture a series of consecutive frames during stop motion, choose Stop Motion > Grab Frames. Specify the number of consecutive frames to capture, and then click OK.
- To delete frames from the end of a stop-motion sequence you captured, choose Stop Motion > Truncate Movie. Drag the slider to find the frame where truncating should begin. All frames after the frame you specify will be removed. Click Truncate.
- To show a ghost image of the previous frame while capturing, choose Stop Motion > Show Previous. This command is useful for positioning the subject of the current frame against the contents of the previously captured frame. The ghost image does not become part of the captured file.
- To remove a background clip, choose Stop Motion > Remove Background Clip. This command is active only if you added a background clip to help position the subject being captured. For information about adding a background clip, see “Importing a sample frame” on page 275.

Reading timecode from source video

On most home VCRs, the tape counter doesn't keep track of specific frames—for example, tape counters on many VCRs reset to zero if you switch tapes or turn the VCR off and on. In contrast, high-end and professional video decks and cameras can record and read *timecode* to and from a videotape, marking specific frames so that it is possible to accurately locate, edit, and synchronize video frames and the audio track. When capturing video, you usually want to capture the timecode associated with each clip if the source video contains timecode. Timecode is essential if you plan to create an edit decision list and create the final video program on a high-end online edit bay instead of in Premiere. Using SMPTE timecode ensures frame accuracy.

When capturing video with timecode, keep in mind the following:

- The timecode of a source video is captured when you use device control. (Capturing with device control requires timecode. See “Using the Movie Capture window” on page 125.)



With device control, you can use videotape timecode (left) to precisely edit a program in Premiere (right).

- Timecode is visible only in the tape counter on equipment that can recognize timecode, unless the timecode has been *burned-in*, or recorded over the picture in a copy of the tape. Most home VCRs cannot read or write timecode.

- If you plan to capture an entire tape, only the In point of the movie needs to be recognized during capture. Once the In point is recorded, a frame-accurate tape deck will capture all of the following frames accurately. The default Out point is beyond the length of your tape; thus, the entire tape can be captured without setting an Out point.

***Note:** Timecode capture with controllable devices depends on the precision of your tape deck. If your tape deck cannot read the timecode accurately, you may have to calibrate your system or manually assign the timecode to your movie by matching frames.*

Manually setting timecode for a clip

On some videotape copies, the timecode appears not on the video track, but as a *window dub* or *window burn* superimposed on each video frame. This window dub lets you see the timecode on a deck that doesn't read invisible timecode. Window dub timecode is also called *burned-in*, or visual, timecode. Because a videotape with burned-in timecode usually doesn't include invisible timecode, clips captured from that tape aren't marked with timecode on your computer. However, you can manually set the timecode for each captured clip. Because this requires referring to the original videotape, this is best done immediately after capturing a clip.

To set timecode manually for a clip:

1 Do one of the following:

- Activate the Clip window containing the clip you want to set.
- Open the clip in the Source view.
- Activate the Project or Bin window containing the clip you want to set, and then select the clip.

2 Choose Clip > Advanced Options > Timecode, specify the following options, and click OK:

- For the first option, type the timecode that matches the frame visible in the clip.
- For Frame Rate and Format, choose options that match the videotape.
- For Set Timecode At, click File Beginning if you typed timecode for the first frame in the clip; otherwise, click Current Frame.
- For Reel Name / Description, type the name of the clip's videotape.

Capturing analog audio

If you want to use audio that is not yet in digital form, you need to capture it. With the proper audio- or video-capture card, Premiere can capture audio that is synchronized with its source video or that is independent of it.

The quality of digitized audio and the size of the audio file depend on the *sample rate* (the number of samples per second) and *bit depth* (the number of bits per sample) of the digitized audio. Also, digitizing stereo audio requires twice as much disk space as mono audio. These parameters, controlled in the Capture Settings section of the Project Settings dialog box, determine how precisely the analog audio signal is represented in digital form. Higher sample rates and bit depths reproduce sound at higher levels of quality, but with correspondingly larger file sizes. If you plan to export or play back the final cut from Premiere, capture audio at the highest quality settings your computer can handle, even if those settings are higher than the settings you'll specify for final export or playback. This provides *headroom*, or extra data, that will help preserve quality if you adjust audio gain or apply audio effects such as equalization or dynamic range compression/expansion; see “Applying and controlling effects” on page 327.

To set the location of a file captured from an audio-only source:

- 1 Choose Edit > Preferences > Scratch Disks and Device Control.
- 2 For Captured Movies in the Scratch Disks section, select a location and click OK.

To capture an audio source (Windows):

- 1 Choose File > Capture > Audio Capture.
- 2 Locate and select the capture program you want to use, and click OK. If you have not purchased a separate audio-capture program, you can use the Windows Sound Recorder (Sndrec32.exe, located in the folder in which you installed Windows). Then click OK.
- 3 Use the audio capture program to record an audio file. See the documentation or online Help for the capture program. (Premiere remembers the program you chose for recording audio. The next time you choose Capture > Audio Capture, Premiere automatically starts the same audio program.)

Note: In Windows, audio input options are affected by the settings in the Multimedia Control Panel and in the capture program you use. For information, see the online Help for Windows and for the capture program.

To capture an audio source (Mac OS):

- 1 Choose File > Capture > Audio Capture.
- 2 Choose Audio Capture > Sound Input.
- 3 Select a Source from the menu. The options available depend on the audio hardware you are using. For example, a capture card's software may add options to this dialog box.
- 4 For Sample Rate, select the number of samples per second. Compact-disc audio is stored at 44.1 Hz. For best results, choose the sample rate that corresponds to the rest of the audio in your project. For example, if your project contains primarily DV audio, choose 48 Hz.
- 5 For Format, do the following:
 - Select a bit depth from the left menu. For voice and medium-quality music, 8-bit sound is sufficient; compact-disc audio is stored at 16 bits. Stereo audio requires twice as much disk space and processing as mono audio.
 - Select the channel usage you want from the right menu.
- 6 For Speaker, select how you want the speakers to function while you record.
- 7 For Volume, drag the slider to amplify or attenuate the incoming audio signal.
- 8 If available, click Options, specify any options provided by your audio hardware, and click OK.
- 9 Click OK to close the Sound Settings dialog box.
- 10 Click Record.

***Note:** If no audio is recorded or you can't hear your source audio, try playing the audio through the computer speaker system without recording. If you still can't hear it, the audio source may not be properly connected. Check hardware connections, settings in the Multimedia Control Panel (Windows) or the Sound or Monitors and Sound control panels (Mac OS), and the documentation that came with your computer and sound card.*

Importing digital audio

Premiere can import digital audio clips stored as audio files or tracks in video files. Digital audio is stored as binary data readable by computers. Most digital audio is stored on computer hard disks, audio compact discs (CDs), or digital audio tape (DAT). If you have capture hardware that can read digital audio data directly, such as an IEEE 1394

(FireWire/i.Link) connection, you can preserve the quality of your digital audio source. Using all digital connections, you can capture digital audio directly into Premiere from the Movie Capture window: make sure to turn off the Take Video option and set your audio source settings in the Movie Capture window menu.

Many computers in their standard configuration import audio through analog input jacks; the digital audio is converted to analog when you use the audio equipment output jacks and converted back to digital when you capture. This additional digital-analog-digital conversion reduces audio quality somewhat.

Audio from individual audio CD tracks are written as individual Compact Disc Audio (CDA) format files. Premiere does not support the CDA format, so you must convert them to a supported format before importing them. Once the digital audio is in a format that Premiere can read, include it in your project using the Import command. See “Importing clips” on page 151.

Note: Make sure that you own the copyrights or have licensed the copyrights to any CD tracks you use.

Using CD audio in Windows

You can play audio CD files from Windows, but before you can import them into Premiere, you need to convert them to a supported file format. You can convert CDA files using third-party conversion applications such as WaveStudio from Creative Labs Inc., Sound Forge from Sonic Foundry, or Audio Grabber from Audio Grabber.

Once you’ve converted the audio file to a WAV or AIFF file format, import it using the File > Import command.

Using CD audio in Mac OS

On Mac OS, you can import audio CD tracks as AIFF or WAV files with no loss of quality, using a converter built into QuickTime.

Note: Although the DV format can record two independent stereo audio pairs, you cannot capture the Stereo 2 pair in Windows, and you cannot capture two stereo pairs independently in Mac OS. Also, Premiere does not currently support creating 4-channel tapes.

To import an audio CD track (Mac OS only):


- 1 In Premiere, choose File > Open. Locate and select the audio CD, and click Open.

- 2 Select a track and click Options.
- 3 Click Play to verify that you've selected the correct track.
- 4 Specify the following options:
 - For Rate, select the number of samples per second. Compact-disc quality is 44.1 kHz.
 - For Size, select the bit depth of the audio. Compact-disc quality is 16 bit.
 - For Use, select whether the track is imported as mono or stereo audio.
- 5 If you want to import only a portion of the entire track, do any combination of the following in the Audio Selection section and then click OK:
 - For Start and End, type times relative to the track duration.
 - Drag the beginning or ending sliders.
- 6 Specify a location and filename to store the converted track, and click OK.

 *Premiere projects containing audio with different sample rates require extra rendering time. To avoid this, resample the audio in the minority of clips that use different sample rates and then replace them in the project. To resample an audio clip, import it into a separate project that is set to the desired sample rate, export it as a movie, and then import the new movie into your project.*

About D1, DV, and various pixel aspect ratios


Pixel aspect ratio specifies the ratio of width to height of one pixel in an image. *Frame aspect ratio* describes the ratio of width to height in the frame dimensions of an image. For example, DV NTSC has a pixel aspect ratio of 0.9 (or 0.9 width by 1.0 height). It also has a frame aspect ratio of 4:3 (or 4.0 width by 3.0 height).



A 4:3 frame aspect ratio (left), and a wider 16:9 frame aspect ratio (right)

Many video formats use the same 4:3 frame aspect ratio but use a different pixel aspect ratio. For example, some NTSC capture cards produce a 4:3 frame aspect ratio, with square pixels (1.0 pixel aspect ratio) and a resolution of 640 x 480. DV NTSC produces the same 4:3 frame aspect ratio, but uses rectangular pixels (0.9 pixel aspect ratio), and a resolution of 720 x 480. DV pixels, which are always rectangular, are vertically oriented in systems producing NTSC video and horizontally oriented in systems producing PAL video.

If you display rectangular pixels on a square-pixel monitor without alteration, images and motion appear distorted; for example, circles distort into ovals. However, when displayed on a broadcast monitor, the images will be correct.



*A. Square pixels and 4:3 frame aspect ratio B. Nonsquare pixels and 4:3 frame aspect ratio
C. Nonsquare pixels displayed on a square-pixel monitor*

When you import or capture DV video, the image looks slightly wider than it does on a D1 or DV system. (D1 PAL footage looks slightly narrower.) The opposite effect occurs when you capture or import anamorphic footage using D1/DV NTSC Widescreen or D1/DV PAL Widescreen. Widescreen video formats have a frame aspect ratio of 16:9.

If a file uses rectangular pixels, Premiere displays the pixel aspect ratio next to the file's image thumbnail in the Project window. You can change the pixel aspect ratio interpretation for individual files in the Pixel Aspect Ratio dialog box. By ensuring that all footage files are interpreted correctly, you can combine footage with different ratios in the same project and generate output that plays correctly.

Premiere sets the pixel aspect ratio for a project according to the preset you choose when starting a project. You can change this setting before editing begins, but once you start editing, changing the pixel aspect ratio can cause problems.

When you capture or import video with either the D1 resolution of 720 x 486, or the DV resolution of 720 x 480, Premiere automatically sets the pixel aspect ratio for that file to D1/DV NTSC (0.9). When you import footage with the D1 or DV resolution of 720 x 576, Premiere automatically sets the pixel aspect ratio for that file to D1/DV PAL (1.067). However, it is always a good idea to make sure all files are interpreted correctly by looking in the Project window or the Pixel Aspect Ratio dialog box.

***Note:** Be sure to reset the pixel aspect ratio to Square Pixels when you import a square-pixel file that happens to have a D1 or DV resolution—for example, an Adobe Photoshop image with a resolution of 720 x 480.*

Setting pixel aspect ratio

It is important to set the pixel aspect ratio for a file at its original ratio, not the ratio of the final output. You can set pixel aspect ratios for clips and projects with these approximate values:

Square Pixels Uses a 1.0 pixel aspect ratio. Use this setting if your video has a 640 x 480 or 648 x 486 frame size.

D1/DV NTSC Uses a 0.9 pixel aspect ratio. Use this setting if your video has a 720 x 480 or 720 x 486 frame size, and your desired result is a 4:3 frame aspect ratio.

D1/DV NTSC Widescreen Uses a 1.2 pixel aspect ratio. Use this setting if your video has a 720 x 480 or 720 x 486 frame size, and your desired result is a 16:9 frame aspect ratio.

D1/DV PAL Uses a 1.0666 pixel aspect ratio. Use this setting if your video has a 720 x 576 frame size, and your desired result is a 4:3 frame aspect ratio.

D1/DV PAL Widescreen Uses a 1.4222 pixel aspect ratio. Use this setting if your video has a 720 x 576 frame size, and your desired result is a 16:9 frame aspect ratio.

Anamorphic 2:1 Uses a 2.0 pixel aspect ratio. Use this setting if your video was shot using an anamorphic film lens.

D4/D16 Standard Uses a 0.9481481 pixel aspect ratio. Use this setting if your video has a 1440 x 1024 or 2880 x 2048 frame size, and your desired result is a 4:3 frame aspect ratio.

D4/D16 Anamorphic 8:3 Uses a 1.8962962 pixel aspect ratio. Use this setting if your video has a 1440 x 1024 or 2880 x 2048 frame size, and your desired result is an 8:3 frame aspect ratio.

To set the pixel aspect ratio for imported files:

- 1 Select the file in the Project window.
- 2 Choose Clip > Advanced Options > Pixel Aspect Ratio.
- 3 Select a ratio from the Pixel Aspect Ratio menu and click OK.

If you are planning to export to the same pixel aspect ratio as your clips, you also need to set the pixel aspect ratio for the project.

To set the pixel aspect ratio for a project:

Do one of the following:

- Choose the appropriate project preset when starting your project.
- If a project is already open, choose Project > Project Settings > Video, and select a ratio from the Pixel Aspect Ratio menu; then click OK.

Using square-pixel footage for output to DV

You can use square-pixel footage in a DV project and generate output that does not appear distorted. Premiere either upsamples (increases) the resolution or downsamples (decreases) the resolution of a file that does not match the project frame size. Because downsampling results in a higher-quality image, it is best to create files that are larger than the project's frame size so that Premiere does not have to upsample and enlarge the file.

To use square-pixel files in a D1 or DV project:

- 1 Prepare square-pixel footage using one of the following methods:
 - If your final output is DV (NTSC), create and save it at a 720 x 540 frame size to prevent upsampling, or 640 x 480 to prevent field distortion on a field-rendered file (such as a 3D animation).
 - If your final output is DV (PAL), create and save it at a 768 x 576 frame size to prevent upsampling and field distortion on a field-rendered file (such as a 3D animation).
 - If your final output is D1 (NTSC), create and save it at a 720 x 540 frame size.
- 2 Capture or import the file into Premiere.

3 If you cannot use the methods from step 1, do whichever of the following is necessary:

- If your square-pixel file was created and saved at an odd size or a smaller frame size than that used by your project (for example, if you imported a 400 x 400 logo prepared in Illustrator or a scanned image intended to be superimposed onto the video), select it and choose **Clip > Video Options > Maintain Aspect Ratio**. The **Maintain Aspect Ratio** option prevents the image from being resized to fit the frame and makes Premiere resample the image using the same nonsquare pixel aspect ratio as the project.
- If your square-pixel file was created and saved at a standard frame size (such as 640 x 480 or 720 x 540), Premiere will scale the image so that the pixel aspect ratio, frame aspect ratio, and frame size match the project. For best results, create files with a frame size in which one dimension matches that of the project and the other is greater than the project—so that Premiere downsamples rather than upsamples.
- If your square-pixel file was created and saved at the frame size used by your project (such as 720 x 480), you'll want to redesign your image using a different frame size (such as 720 x 540).

Importing clips

You can import clips into Premiere as a single clip, multiple clips, or an entire folder of clips directly into the Project window. If you want to examine a clip before importing it into the project, open the clip in a Clip window and then move the clip to the Project or Timeline window. Clips cannot exceed 4000 x 4000 pixels. If the software you use to create art does not let you specify pixels as a unit of measure, specifying points may be sufficient. If the file does not include pixel aspect ratio information, Premiere uses the Interpretation Rules.txt file, which can be customized, to determine the pixel aspect ratio based on codecs, image sizes, and other parameters.

By default, Premiere alters the size and aspect ratio of a video clip or still image to match that of the video frame you specified for your project. Premiere displays images with the correct frame aspect ratio in the Monitor and Trim windows. For more information on aspect ratios, see “About D1, DV, and various pixel aspect ratios” on page 147.

Premiere can import a number of video and audio formats.

Video formats: Type 2 AVI, MOV, and Open DML (Windows only)

Note: *Type 1 AVI clips must be rendered before they can be previewed from your DV device. To render a Type 1 AVI clip, add it to the Timeline in a DV project, and build a preview file of that section of the Timeline.*

Audio formats: AVI, MOV, AIFF, WAV (Windows only), the Macintosh Sound Format, (Mac OS only), and Sound Designer I & II (Mac OS only)

Still-image and sequence formats: AI and AI sequence, PSD and PSD sequence, GIF and animated GIF, Filmstrip, JPEG, PICT and PICT sequence, TGA and TGA sequence, TIFF and TIFF sequence, PCX (Windows only), FLC/FLI (Windows only), BMP and BMP sequence (Windows only), and PICS animations (Mac OS only)

File format support is provided by plug-in software modules. Over time, additional or updated file formats may be available from Adobe or other manufacturers, such as QuickTime.

To import one or more clips into the Project window:

Do one of the following:

- To import a single clip, choose File > Import > File. Locate and select the file, and then click Open.
- To import multiple clips in Windows, choose File > Import > File. Hold down Control as you select each file you want to import, or hold down Shift and select the first and last files of a range you want to import. Click Open.
- To import multiple clips in Mac OS, choose File > Import > File. Hold down Shift as you select each file you want to import. Click Open.
- To import a folder of clips, choose File > Import > Folder. Locate and select the folder you want to import, and then click OK (Windows) or Select *foldername* (Mac OS).

To examine a clip before adding it to the project:

- 1 Choose File > Open.
- 2 Locate and select the file you want to examine, and then click Open. The clip appears in the Monitor source view or in a Clip window.

3 Examine the clip. If you decide to add it to the project, position the pointer inside the clip display and drag it to the Project window or choose Clip > Add Clip to Project.

Note: To control the window in which a clip opens, choose Edit > Preferences > General and Still Image, select or deselect the Open Movies in Clip Window option, and click OK.

Importing still images

You can import individual still images or convert a numbered sequence of still images into a single animation as you import (see “Importing an animation or still-image sequence” on page 155). When you import an individual still image, it uses the duration specified in the dialog box that appears when you choose Edit > Preferences > General and Still Image. You can change the duration of a still image after you import it.

To change the default duration for still images:

- 1 Choose Edit > Preferences > General and Still Image.
- 2 In the Still Image section, specify the number of frames you want as a default duration for a still image.

Note: Changing the default duration of still images does not affect the duration of still images that are part of a sequence.

To change the duration of a still image you have already imported:

Select the clip and choose Clip > Duration. Type the new duration and click OK.

By default, Premiere will alter the size and aspect ratio of a still image to match that of the frame size you specified for your project. You can specify that still images retain their original aspect ratio (see “Maintaining the original aspect ratio of a clip” on page 195). You can also scale an image to a size other than the size of the frame (see “Scaling a clip” on page 189).

If you’re planning to use many still images that use different aspect ratios from your project frame size, you can lock the aspect ratio of each still image before you import it.

To lock the aspect ratios of still images before you import them:

- 1 Choose Edit > Preferences > General and Still Image.
- 2 Select Lock Aspect to preserve the proportions of a still image in Premiere. When Lock Aspect is deselected and you import a still image that has a different aspect ratio than the video frame in the project, Premiere resizes the image to fit.

 *If you import a nonsquare-pixel file that was created and saved at an odd size or a smaller frame size than used by your project (for example, 400 x 400), select it and choose Clip > Video Options > Maintain Aspect Ratio. Then, with the file still selected, choose Clip > Advanced Options > Pixel Aspect Ratio, choose Square Pixels from the Pixel Aspect Ratio menu, and click OK. Setting both of these options prevents Premiere from resizing the image to fill the screen and from resampling the file to match the pixel aspect ratio of the project.*

Importing Adobe Illustrator files

You can import an Adobe Illustrator still-image file directly into a Premiere project. Premiere converts path-based Illustrator art into the pixel-based image format used by Premiere, a process known as *rasterization*. Premiere automatically *anti-aliases*, or smooths, edges of the Illustrator art. Premiere also rasterizes all empty areas in an Illustrator file with an alpha channel premultiplied with white, which means that it can be transparent when you superimpose it over other clips, but you must apply the White Alpha Matte key type. See “Using keys to superimpose and create composites” on page 298 and “Using Black Alpha Matte and White Alpha Matte keys” on page 303.

You can import Illustrator art up to 2000 x 2000 pixels. If you want to define the dimensions of the Illustrator art as it will be rasterized by Premiere, use the Illustrator program (sold separately) to set crop marks in the Illustrator file. For information about setting crop marks in Illustrator, see the product’s documentation.

To rasterize and import an Adobe Illustrator file:

Choose File > Import > File. Locate and select an Illustrator file, and click Open.

Importing Adobe Photoshop files

You can import files from Photoshop 3.0 or later. However, Premiere does not support 16-bit TIFF images created in Photoshop or other graphic applications. You can also import an individual layer from a multilayer Photoshop file. If the Photoshop file uses an alpha channel for transparency, Premiere preserves it. If you superimpose the Photoshop file over another track in Premiere, you can see through the transparent areas marked by the alpha channel. For information about alpha channels and superimposing, see “Using the Alpha Channel key” on page 302.

***Note:** If you have trouble importing a Photoshop file that uses a layer mask or multiple layers, flatten (combine) the layers in the Photoshop file before importing it into Premiere; for information, see the product’s documentation.*

Importing an animation or still-image sequence

You can import an animation contained in a single file, such as an animated GIF. (An *animation* is different from a video in that it is generated synthetically, not by shooting live action.) Premiere can also import a sequence of numbered still-image files and automatically combine them into a single clip; each numbered file represents one frame. Some programs can generate a series of numbered sequence of still images, such as Adobe After Effects and Adobe Dimensions. Images in a still-image sequence cannot include layers, so flatten images that will be part of a sequence. For information on layers and flattening, see the documentation for the application that created the file.

***Note:** Changing the default duration of still images in the Preferences dialog box does not affect the duration of still images that are part of a sequence.*

When creating three-dimensional images or animations that you will be importing into Premiere, use the following guidelines whenever possible:

- Use broadcast-safe color filtering.
- Use the pixel aspect ratio and frame size specified in the project preset that you will be using in your Premiere project.
- Use the appropriate field settings to match your project.

To import numbered still-image files and compile them into a single clip:

1 Do one of the following:

- In Windows, make sure that each still-image filename has the correct file extension, and make sure that all filenames in the sequence contain an equal number of digits at the end of the filename (before the filename extension)—for example, *file000.bmp*, *file001.bmp*, and so on.
- In Mac OS, make sure that all filenames in the sequence contain a suffix of a period followed by an equal number of digits—for example, *File.000*, *File.001*, and so on. You may insert a space between the period and the file number—for example, *File. 000*, *File. 001*, and so on.

2 Choose File > Import > File.

3 Locate and select the first numbered file in the sequence, select Numbered Stills, and click Open.

Importing another project

You can add the contents of an existing project to an open project. For example, you can break up a large project into smaller, more manageable pieces in separate projects, and then import each project into a main project to create the final video program. When you import a project into an open project, the imported project's clips are added to the Project window in a bin named after the imported project. You can import a project's Timeline contents at the beginning, end, or edit line in the open project's Timeline. All of the imported project's special effects, such as transitions and effects, are included. If there are tracks in the imported project that do not match track names in the open project, they are added to the Timeline.

Premiere imports the project as an insert edit: Any clips on all tracks at or after the insertion point are moved later by an amount corresponding to the duration of the imported project. If you import a project at the edit line, it bisects any clips at the edit line. Before importing a project, you may want to examine both projects to anticipate any potential track conflicts, and save the destination project in case importing a project creates results you didn't anticipate.

***Note:** You cannot import a Premiere 5.0 or earlier project directly into a Premiere 6.0 project because of differences in these versions. To import a Premiere 5.0 or earlier project, first convert it to a Premiere 6.0 project by opening and saving it in Premiere 6.0 (see “Opening a project” on page 85). Make sure that both projects have the same timebase. Projects created in Premiere 5.1 or later can be imported directly into a Premiere 6.0 project.*

To merge a project into a currently open project:

- 1 Make sure that the destination project is open.
- 2 Choose File > Import > Project.
- 3 Locate and select the project, and then click Open.
- 4 Click Beginning, Edit Line, or End to specify where in the Timeline you want the imported project to appear, and then click OK.

Analyzing clip properties and data rate

Premiere includes clip analysis tools that you can use to evaluate a file in any supported format stored inside or outside a project. For example, after producing a video clip to be streamed from a Web server, you can use clip analysis tools to determine if a clip you exported has an appropriate data rate for Internet distribution.

The Properties feature provides detailed information about any clip. For video files, analyzed properties can include the file size, number of video and audio tracks, duration, average frame, audio and data rates, and compression settings. You can also use Properties to alert you to the presence of any dropped frames in a clip you just captured.

To see the properties of a clip:**1** Do one of the following:

- If the clip is in the Project window, select it to display a subset of its properties in the top part of the window.
- If the clip is in the Project, Monitor, or Timeline window, select it, choose File > Get Properties For, and select the filename of the clip.
- If the clip is not yet in the project, choose File > Get Properties For > File. Locate and select the clip you want to analyze, and then click Open.

2 To save the Properties window text as a text file, choose File > Save As, specify a location and filename, and click Save.

3 To see the Data Rate Graph, click Data Rate.

Use the data rate graph to evaluate how well the output data rate matches the requirements of your delivery medium. It charts each frame of a video file to show you the render keyframe rate, the difference between compression keyframes and differenced frames (frames that exist between keyframes), and data rate levels at each frame. The Data Rate Graph includes the following:

- Data rate: the white line represents the average data rate.
 - Sample size: the red bars represent the sample size of each keyframed frame.
 - Differenced frames sample size: the blue bars represent the sample size of the differenced frames between compression keyframes.
- 4** When you are finished, close the Data Rate Graph window and the Properties window.



You can also view clip properties from a window containing a clip by right-clicking a clip (Windows) or pressing Control as you click a clip (Mac OS) and choosing Get Properties.

Using offline files

Premiere automatically creates an *offline file*, or placeholder, for any source file used in the project that it cannot locate when you open a project. You can also create an offline file at any time. For example, if you expect to use source video that has not yet been captured, you can create an offline file as a temporary substitute for the missing source video during editing. When the actual source video becomes available, you can quickly replace all instances of the offline file in a project with the actual source. See “Opening a project” on page 85.

To create an offline file:

- 1 Choose File > New > Offline File.
- 2 Type a filename. In general, use the filename of the actual source video that is missing.
- 3 For Duration, type the length for the offline file.
- 4 For Timecode, type the timecode value of the In point of the missing source video.
- 5 For Reel Name, type the name of the reel containing the missing source video.
- 6 Choose a time format from the Format menu that corresponds to the source video.
- 7 Choose a frame rate from the Speed menu.
- 8 Select either or both Has Video or Has Audio, according to the contents of the source video. Then click OK.

To replace an offline file with a source video file:

- 1 In a Project or Bin window, select the offline file.
- 2 Choose Project > Replace Clips.
- 3 Locate and select the actual source video file, and click OK.

***Note:** If you cannot locate the file, press the Escape key to exit the dialog box and leave the project in its original state.*

http://



3



Chapter 3: Editing Video

The concept of video editing is simple: You arrange a set of video clips in the desired order. In reality, editing a video program can require many iterations as you refine the editing decisions that make all your clips flow together smoothly. Premiere is designed to help you solve the wide range of editing challenges that an unfinished video can present.

This chapter describes how to use the Monitor, Timeline, and Project windows to build a video program. You'll learn how to designate an *In point* (the first frame of a clip that will appear in the video program) and an *Out point* (the last frame that will appear in the video program) for each of your clips. As you read this chapter and the ones that follow, keep in mind that there is no set order in which tasks must be performed, and that Premiere often provides more than one way to accomplish a task. This flexibility lets you adapt how you use Premiere to match the requirements of your work.

Using the Monitor window

The Monitor window displays individual frames of clips and the video program. Using the Single-Track Editing workspace, the Monitor window resembles the monitors in a conventional edit bay with one monitor for the *source*, or source clip, and another for the *program*, or edited video in the Timeline. Controllers at the bottom of the Monitor window are like the edit controller in an edit bay. You can edit clips in either the Monitor window or the Timeline window. See “Editing a video program” on page 197. (A *source clip* is a clip outside the Timeline or in the Source view of the Monitor window; a *program clip* is a clip in the Timeline or Program view of the Monitor window.)

In *Dual View*, the source and program are displayed side by side. You can also choose other views for the Monitor window. If you want to see only the program view, you can select *Single View*. For precise control over trimming, you can switch the Monitor window to *Trim mode*, as explained in “Using the Trim view” on page 219.

If you prefer the window layout used by previous versions of Premiere, you can change the window layout accordingly.


Displaying a clip

Clips can display in either in the Source view (left side) of the Monitor window or in a Clip window. If you want to compare several clips, you can open a window for each.

To view a clip:

Do any of the following:

- To view a clip in the Source view, double-click the clip in a Project, Bin, or Timeline window. Premiere displays the clip and adds its name to the Source menu below the Source view.
- To see up to 35 clips you previously viewed since opening the current project, choose the name of the clip from the Source menu below the Source view.




Selecting a clip to view from the Source menu

- To add multiple clips to the Source menu simultaneously, drag multiple clips or an entire bin from a Project or Bin window into the Source view, or select multiple clips in a Project or Bin window and double-click them.
- To change the Source view time display, choose Monitor Window Options from the Monitor window menu. In Source Options, choose a Count from the menu. The Count designates the format of the clip's timecode display. Select Zero Based if you want to start the clip's timecode at zero instead of using the timecode of the clip's first frame. Click OK.
- To open the currently visible Source view clip in its own window, press Alt (Windows) or Option (Mac OS) as you double-click the clip in the Source view.

- To always open a clip in its own window, choose Edit > Preferences > General & Still Image, select Open Movies in Clip Window, and click OK.
- To override the current window preference for opening clips (described in the previous paragraph), press Alt (Windows) or Option (Mac OS) as you double-click a clip in the Project window. For example, if you set the preference to open clips in their own windows, pressing Alt/Option opens a clip in the Source view.
- To view a clip that isn't already in a Project or Bin window, choose File > Open, locate and select the clip, and click Open.

Viewing safe zones

Television sets enlarge a video image and allow some portion of its outer edges to be cut off by the edge of the screen. This is known as *overscan*. The amount of overscan is not consistent across television sets, so you should keep important parts of a video image, such as action or titles, within margins known as *safe zones*. You can view safe zones in the Monitor window's Source view, Program view, or both.



To view safe zones in the Monitor window:

In the Monitor window menu, choose Safe Margins for Source Side or Safe Margins for Program Side. Choose either menu item again to remove the corresponding safe zones from the Monitor window.

To change the dimensions of the safe zones:

- 1 In the Monitor window menu, choose Monitor Window Options.
- 2 For Action-Safe Margin and Title-Safe Margin, type new values representing the percentage of the full Program or Source view window *not* included in the safe zones. Click OK.

Using Monitor window controllers

The Monitor window contains similar controllers for the Source and Program views, which you use to view and find frames in a clip or video program. Many of the controllers work like the tape transport controls on a video deck. They serve the following purposes:

- Use the Source controller (under the Source view) to play or view the frames of a source clip and to specify the clip's *source In and Out points*, which define the portion of the clip that will be added to the program. (The first frame that will be added is the source In point, and the last frame that will be added is the source Out point.)
- Use the Program controller (under the Program view) to play or view the video program in the Timeline and to specify a clip's *program In and Out points*, which define where the clip's In and Out points are on the Timeline.

When you want to use a controller to navigate a clip or the program, first make sure that the correct controller is active. When a controller is active, its timecode readout is green, and the view above it is outlined with the highlight color set for your computer. The number at the bottom right of each controller is the current time position for that view. The number preceded by a delta symbol (Δ) at the bottom left of each controller is the time difference between the In point and the Out point of the currently displayed source clip or video program.



In the Monitor window, you can cycle through time display options by pressing Control (Windows) or Command (Mac OS) as you click a timecode readout. The time display options cycle in the order they appear in the Count menu (available when you choose Window > Monitor Window Options when the Monitor window is active).

To customize the Monitor window view:

Do any of the following:

- To set the active view and controller, click the Source or Program view.

- To limit the view to the Program view, click the Single View button (□) at the top of the Monitor window. You can also choose Single View from the Monitor window menu.
- To return to the Source/Program view, click the Dual View button (▣) at the top of the Monitor window.

To play the Source or Program view:

Do any of the following:

- To play, click the Play button (▶).
- To stop, click the Stop button (■).
- To play from the In point to the Out point, click the Play In to Out button (▶|◀).
- To play from the current time to the Out point, Alt-click (Windows) or Option-click (Mac OS) the Play In to Out button (▶|◀).
- To play and loop, click the Loop button (♻).
- To play in reverse, press Ctrl+Alt and click the Play button (Windows) or press Command+Option and click the Play button (Mac OS).
- To play faster, click the Play button. Repeatedly clicking the button increases speed further.
- To play including preroll and postroll, press Alt (Windows) or Option (Mac OS) as you click the Play button. *Preroll* starts playback from a time before the In point, and *postroll* stops playback at a time after the Out point. Set preroll and postroll values in the General/Still Image Preferences dialog box.

To view a different frame:

Do any of the following:

- Make sure that the view you want is active, and on the numeric keypad type the new time. You do not need to type colons because Premiere converts the numbers automatically.
- To display the same frame in the Program view that is displayed in the Source view, make sure that the Source view is active and that the current Timeline instance of the Source view clip is displayed (the name of the clip and its In point will be in the Select Source Clip menu below the Source view), and then press T.

- To display the same frame in the Source view that is displayed in the Program view, make sure either the Program view or Timeline is active, and then press T. This will display the corresponding frame in the actual source clip, not its Timeline instance.
- To go forward one frame, click the Frame Forward button (▶).
- To go forward five frames, press Shift as you click the Frame Forward button (▶).
- To go backward one frame, click the Frame Back button (◀).
- To go backward five frames, press Shift as you click the Frame Back button (◀).
- To go to the previous edit in a target audio or video track, click the Previous Edit button (⏮) in the program controller. (An *edit* is where a program clip ends or begins in the video or audio tracks.)
- To go to the next edit in a target audio or video track, click the Next Edit button (⏭) in the program controller.

Note: *In the Single-Track Editing mode, the Previous and Next buttons also stop at the cutpoint of each transition when the Video 1 track is expanded, and at audio cuts.*

- To go to the first frame of the video program, press the Up Arrow key.
- To go to the last frame of the video program, press the Down Arrow key.

For more information, see “Moving around in the Timeline” on page 176.

The Monitor window controllers also include a *jog tread* and a *shuttle slider*. The shuttle slider marks the position of a frame relative to the beginning and end of the clip (in the Source view) or Timeline (in the Program view). However, because the shuttle slider is a fixed width, it is less precise when you are looking at long clips or programs. The jog tread is helpful in these cases, because you can navigate finer increments of a clip or program than with the shuttle slider. The timecode readout updates in the Source view or Program view as you jog or shuttle.

To jog or shuttle through frames:

Do one of the following:

- Click in the shuttle slider area.
- Drag the shuttle slider.

- Drag the jog tread left or right, past the edge of the controller if necessary, until you reach the frame you want. If you drag the cursor to the edge of the screen without reaching the end of the clip or program, you can continue from the same time position by starting another drag from the jog tread.

 *If you are trying to find a frame and know its approximate location within a clip, start by clicking in the shuttle slider area in the general location of the frame and then drag the jog tread to look carefully in that area.*

Selecting an editing workspace

The style of editing you use when working in Premiere depends on the task at hand, such as assembling a rough cut of a project or doing more precise editing. Premiere provides predefined editing workspaces that you can quickly and easily set up for the style of editing you want to use. Four editing workspaces are available: A/B Editing, Single-Track Editing, Effects, and Audio.

A/B Editing mode is intended primarily for editors who wish to work by dragging clips from the Project window to the Timeline window. This mode resembles a conventional editing method called *A/B roll editing*, which uses two video tapes or rolls (A and B) and an effects switcher to provide transitions. Selecting A/B Editing sets up the following conditions:

- In the Monitor window, Single View is selected.
- Clips open in a separate clip window.
- In the Timeline window, the Video 1 track displays three subtracks: Video 1A, 1B, and the transition track.
- All palettes are available, with the Effect Controls, Navigator, and Transitions palettes active.

Single-Track Editing mode is intended for trimming and positioning clips by setting In and Out points in the Source view of the Monitor window, and inserting and overlaying the trimmed clips into the Timeline window. For basic video programs, such as a *cuts-only* (no transitions) rough cut, you may want to use Single-Track mode. All tools act on the three subtracks as a single track when they are combined in Single-Track Editing mode. Selecting Single-Track Editing sets up the following conditions:

- In the Monitor window, Dual View (Source/Program) is selected.

- Clips open in the Source view window.
- In the Timeline window, the video and transition tracks are combined.

Effects mode is intended for easy access to both audio and video effects. Selecting Effects sets up the following conditions:

- In the Monitor window, Single View is selected.
- Clips open in a separate clip window.
- The Info palette is grouped with the Effect Controls palette and the Transitions, Video, and Audio palettes are separate and active.

Audio mode is intended for easy access to the tools necessary for editing audio tracks. Selecting Audio sets up conditions identical to the Effects mode, except the Audio Mixer window is open.

Managing the window workspace

When you start Premiere for the first time, or after deleting or renaming the Preferences file, you are prompted to select the editing workspace. You can also select a different editing workspace at almost any time while working on a project. You can also create custom window layouts by rearranging the windows and changing their settings.

You can save your favorite custom window layouts and apply them to any project. Saving a workspace preserves the locations of Project, Monitor, Timeline, and Audio Mixer windows. Other windows, such as the Clip window, are not saved. However, no window option settings are saved with workspaces.

***Note:** You should not switch between A/B Editing and Single-Track Editing modes, as it is possible in A/B mode to place clips in positions which are not allowed in Single-Track mode.*

To save a custom window workspace:

- 1 Arrange the Project, Monitor, Timeline, and Audio Mixer windows the way you want them, including size, location, and settings.
- 2 Choose Window > Workspace > Save Workspace.
- 3 Type a name for the workspace, and click Save. The new workspace is added to the Workspace menu.


To select or delete a custom workspace:

- To select a workspace, choose Window > Workspace and then choose the name of a workspace.
- To delete a workspace, choose Window > Workspace > Delete Workspace, choose a name, and click Delete.

 Because new workspaces appear on the Window > Workspace submenu, you can also add a workspace to the Commands palette. See “Using the Commands palette” on page 102.

Using the Timeline window

The *Timeline* is a time-based view of your program where you can select, arrange, and modify the instances of the source clips you’ve used in the video program. The Timeline graphically shows the placement of each clip in time, its duration, and its relationship to the other clips in the program.



A. Work area markers **B.** Preview indicator area **C.** Work area bar **D.** Edit line marker **E.** Work area band
F. Timeline window menu **G.** Selection tool **H.** Superimpose Track **I.** Toggle Track Output icon **J.** Video 1 tracks
K. Audio track **L.** Track Header buttons **M.** Lock icon **N.** Time Zoom Level popup **O.** Track Options Dialog button
P. Toggle Snap to Edges button **Q.** Toggle Edge Viewing button **R.** Toggle Shift Tracks Options button
S. Toggle Sync Mode button

Customizing the Timeline window

You can customize the Timeline display, including how it represents clips when you view or edit them in the Timeline. For information on customizing the Timeline's *tracks*, see "Customizing track views" on page 173.

To customize the Timeline window:

- 1 In the Timeline window menu, choose Timeline Window Options.
- 2 In the Icon Size section, select the size of the preview icon you want in the Timeline. If you expect to use many tracks or work on a small monitor, choosing a small icon size will make it possible to display more tracks.
- 3 In the Track Format section, select an option:
 - The first option displays sample frames along the duration of a clip. This option makes it easier to find a frame, but slows display and does not include the filename.
 - The second option displays the clip's poster and ending frames as well as the filename.
 - The third option displays the poster frame and the filename.
 - The fourth option displays the filename only. This option displays the fastest.
- 4 In the Audio section, choose an option from the drop-down menu. This option indicates the time zoom level at which an audio waveform will be visible in the Timeline.
- 5 In the Options section, specify the following options as necessary, and then click OK:
 - From the Count menu, select the unit of time displayed in the Timeline.
 - Specify a Zero Point if you want the starting timecode for the video program to be other than 00:00:00:00. This option also sets the starting timecode when you export an EDL.
 - For On Insert, select Shift Material in All Unlocked Tracks if you want all tracks to move when you insert a clip into the Timeline, or select Shift Material Only in Target Tracks if you want only the target tracks to be affected when you insert a clip. To alternate between these two options, click the Toggle Shift Tracks Options button (⌘⇧) at the bottom of the Timeline window.
 - Select Show Markers to display clip and Timeline markers. Deselect this option if the Timeline contains many markers and if you want to view the Timeline with less clutter. See "Using markers" on page 185.

- Select Block Move Markers to move Timeline markers when you move unlocked tracks by using the multitrack select tool or by performing an insert or ripple edit when Shift Material in All Unlocked Tracks is selected. Deselect this option if you want Timeline markers to remain in place. This option does not affect clip markers. Markers do not move for any tool except the multitrack tool.

 *In the Timeline, you can cycle through each time display option by pressing Ctrl (Windows) or Command (Mac OS) as you click the time ruler. The time display options cycle in the order they appear in the Count menu in the Timeline Window Options dialog box, described earlier in this section.*

Customizing track views

Depending upon the Workspace, the Video 1 track will display one of two ways. In A/B Editing mode, it displays as three subtracks: Video 1A, 1B, and the transition track. In Single-Track Editing mode, the three subtracks are combined. In this mode, the Video 1 track can display as either collapsed or uncollapsed. When it is collapsed, all clips and transitions are combined on one track. When it is uncollapsed, the view resembles that of the A/B Editing mode, except you cannot overlap the clips, and the separate tracks still behave as one track. You get only a visual representation of the overlap. The uncollapsed view is useful for obtaining a more accurate view of the transition overlaps. Choose between the collapsed and uncollapsed views by clicking the Track Mode button.

Track modes are activated automatically when you select a workspace for editing. See “Selecting an editing workspace” on page 169. The setting of the Track Mode button is saved in both the project file and in the Premiere preferences file.


In both editing modes, the Video 2 track, by default, is available for superimposing clips over the Video 1 tracks, and you can add more tracks for additional layers of superimposed video. Similarly, you can use Premiere’s multiple audio tracks to overlap sound. To add video and audio tracks, see “Adding, naming, and deleting tracks” on page 177.

You can put a video clip on any video track and an audio clip on any audio track. However, to use a transition, there must be a video clip on a Video 1 track. If you intend to superimpose a video track, it must be on any track *other* than Video 1. If your project uses more tracks than the Timeline can display, you can resize the Timeline window or scroll vertically to see the tracks that are out of view. You can also control the proportion of space taken by video and audio tracks, condense the vertical space of tracks by collapsing them, or hide tracks. Finally, you can prevent tracks from being included when you preview, play back, or export the video program.

To collapse or uncollapse the Video 1 track in Single-Track Editing mode:

- Click the Track Mode button (⌘) to the right of the Video 1 track name.


Note: In Premiere 5.0, these modes were selected using the triangle in the track header, which in this version is used to display or hide keyframes and fade controls.



Track Mode button in Single-Track collapsed mode (left) and Single-Track uncollapsed mode (right).

To resize the track heading section of the Timeline window:

Position the pointer over the right edge of the track heading section so that the resize tool (⬄) appears, and then drag the right edge.



The track heading section: being moved by the resize tool (left) and after the move (right)

The editing tools in the upper left corner limit the minimum width of the track header.

To change the proportion of video and audio tracks displayed in the Timeline:

Drag the split-window bar, located at the right side of the Timeline between the Video 1 and Audio 1 tracks. This feature works best when there are many video or audio tracks in a large Timeline window.

Hiding and excluding tracks

You can mark any track as *shy*, which means it can be hidden in the Timeline. Marking a track as shy does not immediately conceal it in the Timeline, because you must choose the Hide Shy Tracks command to conceal or reveal all shy tracks simultaneously. Shy and hidden tracks are included in the previews and exported program even when they are not visible in the Timeline. You can also exclude a track from a program. An excluded track still appears in the Timeline but is not included either in exported video or when previewing or scrubbing the Timeline.

Hiding and excluding tracks reduces timeline clutter and increases scrolling or previewing performance. Excluding a track also allows comparison between different versions of the program. Shy, excluded, and hidden tracks can still be edited as normal tracks. To make sure that hidden tracks are not edited, lock them before hiding them. See “Locking and unlocking tracks” on page 180.

To hide or reveal tracks in the Timeline:

1 Do one of the following:

- To mark a track as shy, press Ctrl (Windows) or Command (Mac OS) as you click the eye icon (👁️) (for video) or speaker icon (🔊) (for audio) at the left edge of a track. The icon then appears as an outlined eye (👁️) (for video) or outlined speaker (🔊) (for audio).
- To mark a track as not shy, press Ctrl (Windows) or Command (Mac OS) as you click an outlined eye icon (👁️) (for video) or speaker icon (🔊) (for audio).
- To mark as shy (or not shy) all superimposed video tracks or all audio tracks, press Ctrl+Alt (Windows) or Command+Option (Mac OS) as you click to modify the eye or speaker icon at the left edge of any track except Video 1.

2 In the Timeline window menu, choose Hide Shy Tracks or Show Shy Tracks from the Timeline window menu.

To exclude or include a track in the program:

Click to hide or display the eye icon (for video) or speaker icon (for audio) at the left edge of a track.

To simultaneously exclude or include all tracks except Video 1 in the program:

Press Alt (Windows) or Option (Mac OS) as you click to hide or display the eye icon (for video) or speaker icon (for audio) at the left edge of any track. This excludes or includes all superimposed video tracks or audio tracks; you must include or exclude tracks Video 1A/1B separately.

Moving around in the Timeline

The *time ruler* at the top of the Timeline displays the current time position of the edit line and any markers that have been set in the Timeline (see “Using markers” on page 185). From the time ruler, you can view the location of the In and Out points of a clip and the duration of the entire video program. When you do anything that repositions the edit line, such as clicking the Frame Forward button, you change the current frame in the Monitor Program view.

To position the edit line in the Timeline:

Do any of the following:

- In the Timeline, drag the edit line or click the ruler at the point where you want to position the edit line.
- In the Monitor window, select the Program timecode, type a new number on your keypad, and press Enter (Windows) or Return (Mac OS).
- In the Monitor window Program view, drag the jog tread or shuttle slider.
- In the Monitor window, click the Frame Back, Frame Forward, Next Edit, or Previous Edit button in the Program controller. See “Using Monitor window controllers” on page 166.
- In the Navigator palette, press and hold Shift as you drag within the representation of the Timeline, or click the timecode and type new timecode using the numeric keypad.

To display the Timeline in more detail:

Do one of the following:

- Select the zoom tool () and then click (or drag a rectangle around) the part of the Timeline you want to see in more detail.
- In the Navigator palette, drag the slider to the right, or click the Magnify icon (.

- Select a smaller time increment from the Time Zoom Level menu at the bottom of the Timeline.

To display more of the program in the Timeline:

Do one of the following:

- Select the zoom tool (⌘) and then press Alt (Windows) or Option (Mac OS) as you click an area in the Timeline.
- In the Navigator palette, drag the slider to the left, or click the Reduce icon (⏪).
- Select a larger time increment from the Time Zoom Level menu at the bottom of the Timeline.

Adding, naming, and deleting tracks

The Timeline can contain up to 99 video and 99 audio tracks. You can add or remove tracks at any time, except for the Video 1, Video 2, Transition, Audio 1, Audio 2, and Audio 3 tracks, which cannot be deleted. New video tracks appear on top of existing video tracks, and new audio tracks appear below existing audio tracks. Deleting a track removes all clip instances on the track but does not affect source clips that you stored in the Project window. You can also change the name of any video or audio track. You cannot delete or rename the Transition track.

To add one track:

In the Timeline window menu, choose Add Video Track or Add Audio Track.

To add, delete, or rename several tracks:

- 1 In the Timeline window menu, choose Track Options, or click the Track Options Dialog button (⌘) at the bottom of the Timeline window.
- 2 Do one of the following, and then click OK:
 - To add tracks, click Add, type a value for Add _ Video Tracks and a value for Add _ Audio Tracks as desired, and click OK.
 - To delete tracks, select one or more tracks to delete, and click Delete.
 - To rename a track, select a track, click Name, type a new name, and click OK. You cannot rename the Video 1B track.

Specifying source and target tracks

When you add clips to the Timeline by dragging, the clip is added to the track and time position where you drop it. However, when you add clips to the Timeline using Monitor window controls or the keyboard, Premiere cannot know exactly how and where you want a clip to be added. In such a case, you must specify in advance the way a source clip's video and audio are added to the Timeline. By default, both source audio and video are added; in the Timeline, the Video 1A and Audio 1 Timeline tracks are the default *target* (destination) video and audio tracks. In the Timeline, the names of the target video and audio tracks are highlighted.

You can control how source video and audio are added to the Timeline using the Take icons and Target menus:

- The Take Video () and Take Audio () icons in the Monitor window control whether a particular source clip's video or audio is added to the Timeline. For example, if one clip contains video that you don't want to use, you can specify that the source clip will provide only audio to the Timeline.
- The video and audio Target menus control the video program in the Timeline. They govern which Timeline video or audio track is set to receive the video or audio track from the source clip. It is possible to target no Timeline track for either video or audio. For example, if you build a rough cut of a music video and the only audio you want to use is a music clip separate from any of your video clips, you may want to target no audio tracks so that your program receives no audio from any source video clip. If you do this, no audio is added to the program regardless of how you set the Take icons for the source, and the same is true for targeting video tracks.
- Watch out for cases where the target tracks do not match the settings for the source video and audio. For example, if you turn on Take Video but turn off Take Audio for the source clip, but Timeline tracks are targeted for both video and audio, the video goes to the target video track as expected, but the source clip audio duration is inserted in the target audio track as empty space. This is because targeting a track always adds the duration of the source clip even if the corresponding source track (audio or video) is not available to the target. If you don't want the blank audio, specify no target audio tracks.

The way that clips are added to the Timeline depends on not just the interaction of Take icons and target tracks but also the current states of other track and clip options. Certain combinations of these factors may cause unintended tracks to shift in time. For information on relinking clips that have moved out of sync, see “Linking video and audio clips in the Timeline” on page 217.

Note: *The Take Video icon, Take Audio icon, and Target menus affect a clip only during the process of adding it to the Timeline. They don't otherwise change the state of clips.*

To set up Take Video and Take Audio icons and target program tracks:

Do any of the following to specify how video and audio tracks are added to the Timeline:

Note: *A deselected Take Video or Take Audio icon has a red diagonal line across it.*

- To include the source clip's video, make sure that the Take Video icon () below the Source view is selected (if it is deselected, click the icon to select it). Then make sure that a Timeline video track is selected in the Target menu below the Program view; if necessary, choose a video track.
- To include the source clip's audio, make sure that the Take Audio icon () below the Source view is selected (if it is deselected, click the icon to select it). Then make sure that a Timeline audio track is selected in the Target menu below the Program view; if necessary, choose an audio track.
- To include only source video, make sure that the Take Video icon () below the Source view is selected (if it is deselected, click the icon to select it). Choose a target video track from the first (video) Target menu below the Program view, and then make sure that None is selected in the second (audio) Target menu.
- To include only source audio, make sure that the Take Audio icon () below the Source view is selected (if it is deselected, click the icon to select it). Make sure that None is selected in the first (video) Target menu below the Program view, and then choose a target audio track from in the second (audio) Target menu.

 *You can also specify a target track by clicking the name of a track in the Timeline (it then displays in boldface). Clicking a boldface name (the current target track) is the same as choosing None from a target track menu—the track is no longer the target, and its name is no longer in boldface.*

Locking and unlocking tracks

Locking an entire track is useful for preventing changes to any clips on that track while you work on other parts of the program. A locked track is included when you preview or export the program. If you lock the target track, it is no longer the target, so source clips cannot be added to it until you unlock it and then target it. A locked track is marked by a lock icon next to the track name. If you position the pointer or a tool over a locked track, the pointer appears with a lock icon (🔒) to remind you that the track is locked. Locked tracks are dimmed in the Target menus below the Program view. If you want to lock both a video track and a track with corresponding audio, lock each track separately.

You can also lock a clip. This is useful when you don't want to lock an entire track. See “Locking and unlocking clips” on page 196.

To lock or unlock a track:

Click to display or hide the lock icon (🔒) next to the track name.

Editing In and Out points

Most clips are captured with extra footage at the beginning and end to allow for more precise editing later. It's common to fine-tune the beginning and end of a clip just before moving a clip into the program. Define the beginning of the clip by marking an *In point* (the first frame that will appear in the video program), and define the ending by marking an *Out point* (the last frame that will appear in the video program).

Marking and finding In and Out points

For numerical precision, set In and Out points using the Monitor Source or Program view. For visual precision, or if you prefer to use the mouse, edit directly in the Timeline using the edge trim tool. This interactive tool is useful for a rough cut, but it can also be as precise as specifying In and Out points numerically if you set the Timeline to display individual frames in the Time Ruler (see “Moving around in the Timeline” on page 176). The pointer automatically changes to the edge trim tool when you move the selection tool near the edge of a clip in the Timeline.

For linked clips, the video and audio portions can have their own set of In and Out points, called *split points*. Split points are used to create split edits, such as an L-cut, in which the audio extends into the next clip. You can mark split points only when the Source view contains a linked clip. If you bring a linked clip into the Source view from the Timeline, be sure that Sync mode is selected first. For more information on Sync mode, see “Linking video and audio clips in the Timeline” on page 217.

To mark or remove In and Out points using the Source or Program view:

1 Do one of the following:

- To edit In and Out points for a source clip, open a clip from a Project or Bin window.
- To edit In and Out points of a clip already in the program, double-click a clip in the Timeline. (If this is a linked clip and you want to mark split In and Out points, be sure that Sync mode is selected before you double-click the clip.)

2 In the Monitor window, click the view (Source or Program) in which you want to work with In and Out points.


3 Do any of the following:

- To mark an In point, go to the frame you want, and then click the Mark In button (⌘).
- To mark an Out point, go to the frame you want, and then click the Mark Out button (⇧).
- To clear an In point, press Alt (Windows) or Option (Mac OS) as you click the Mark In button.
- To clear an Out point, press Alt (Windows) or Option (Mac OS) as you click the Mark Out button.
- To clear both the In and Out points, press G.
- To make a split In or Out point, right-click (Windows) or Control-click (Mac OS) in the Source view or Program view, and then choose Set Clip Marker and Video In, Video Out, Audio In, or Audio Out, depending on the split point you want.
- To edit a split In or Out point, press and hold Alt (Windows) or Option (Mac OS) and drag the point in the Shuttle Controls.

4 If you opened a clip from the Timeline, click Apply above the Source view to make your changes take effect. (The Apply button doesn’t appear when you prepare a new clip for the Timeline, because your In and Out points are automatically applied when you add the clip to the Timeline.)

To edit clip In and Out points in the Timeline:

- 1 To see the edge frame change in the Program view as you drag, choose Edge View from the Timeline window menu or click the Toggle Edge Viewing button (⌘) at the bottom of the Timeline window.
- 2 Click the selection tool (⌘) and do one of the following:
 - To edit the In point, drag the left edge of the clip.
 - To edit the Out point, drag the right edge of the clip.



A clip while the out point is being edited (left) and after the edit (right)

To find a clip's In or Out point:

- 1 Do one of the following:
 - For a clip's source In or Out point, open the clip and activate the Source or Clip window.
 - For a clip's program In or Out point, open the clip and activate the Program view.
- 2 Choose Clip > Go to Clip Marker > In, or Clip > Go to Clip Marker > Out.

Marking In and Out points for a duplicate clip

If you're working with a duplicate clip that was trimmed (see "Using named duplicate clips and unnamed instances of clips" on page 183), you may want to set a new In or Out point beyond the In and Out point of the duplicate clip. You can do this by opening the duplicate clip's master clip.

To mark In and Out points beyond the current start and end of a duplicate clip:

- 1 Double-click the duplicate clip's master clip in the Project window to open it in the Source view.

- 2 If you don't want to trim the master clip, create a new duplicate clip. See "Using named duplicate clips and unnamed instances of clips" on page 183.
- 3 Set new In and Out points.

Setting an audio source In point between timebase divisions

You can set the source In point of an audio clip to either the individual frames or the audio samples in a clip. For example, when editing a motion picture for film, you might want an audio clip of a finger snap to start playing the instant that sound is heard, but you may find that the motion-picture time display of 24 frames per second (initially set to match the timebase) is too coarse to start playing the audio when you want. You can use the Frames/Samples time display option to set a source audio In point more precisely than one timebase unit, although the project timebase still determines where the source Out point can appear in the Timeline.

To set a source In point between timebase divisions:

- 1 Open the clip in the Source view or in a Clip window.
- 2 Choose Window > Window Options > Monitor Window Options or Window > Window Options > Clip Window Options, depending on the window in which you opened the clip.
- 3 For Count, select Frames/Samples, and click OK. Now the playback controls will operate among individual frames or samples instead of using the project timebase.
- 4 Mark the In and Out points for the clip. See "Marking and finding In and Out points" on page 180.
- 5 If you want to set the count back to the previous setting, choose Window > Window Options > Monitor Window Options or Window > Window Options > Clip Window Options, select the original time display from the Count menu, and click OK.

Using named duplicate clips and unnamed instances of clips

You can use a clip multiple times in the Timeline. The original source clip is called a *master clip*, and each time you add the same master clip to the Timeline, you create a new *instance* of that master clip. Premiere automatically keeps track of each instance of a clip by numbering them in the Project window, but it doesn't list them. If you want a clip instance

to be listed in the Project window, create a *duplicate clip*. A duplicate clip is useful when many or all of the scenes you want to use are in one long clip. Instead of capturing each scene separately and managing a number of different captured files, you can simply capture one long clip and create a named duplicate clip for each scene.

A master clip is a reference to an actual file on disk. An instance refers to the master clip in the project, so if you delete the master clip, its instances are also deleted. A duplicate clip is an independent copy of its master clip that refers directly to the source file on disk; if you delete the master clip, duplicate clips created from it remain in the project. Creating a duplicate clip doesn't create any new files on disk. Other than the differences described here, working with instances and duplicate clips is the same as working with a master clip.

When you double-click an instance or a duplicate clip in the Timeline, it appears in the Source view and is added to the Source view menu, which identifies each duplicate clip by name, and each instance by the timecode of its program In point (where the source In point appears in the program).

To create a duplicate clip:

- 1 In the Project window, select the clip for which you want to create a named duplicate clip.
- 2 To create a duplicate clip for just a portion of the master clip, double-click the clip to open it, and set the In point and Out points to define the frames you want to include in the duplicate clip. See “Editing In and Out points” on page 180.
- 3 Choose Edit > Duplicate Clip.
- 4 Name the duplicate clip and then choose a Location. If you have any Bin windows open, they will also appear in the Location menu along with the Project window.
- 5 Click OK. Premiere stores the new reference to the master clip in the window you specified.

 *You can also create a duplicate clip by copying a clip in a Project or Bin window and then pasting to any of those windows, or by dragging a clip from the Source view to the Project or Bin windows. If you choose to copy and paste the clip, you will not have a chance to name it until you paste it in its new location. Copying from or pasting to the Timeline creates the same effect as dragging to or from the Timeline—Premiere creates another instance of the clip, not a duplicate clip.*

Using markers

Markers indicate important points in time and help you position and arrange clips. The Timeline and each clip can individually contain its own set of up to ten markers numbered from 0 to 9. In addition, the Timeline and each clip can individually contain up to 999 unnumbered markers. Working with markers is much the same as working with In and Out points; markers are only for reference and do not alter the video program (except for markers set up as Web links). In general, add a marker to a clip for important points within an individual clip, and add a marker to the Timeline for significant time points that affect multiple clips, such as when you need to synchronize video and audio on different clips.

When you add a marker to a clip in Source view or the Clip window, it and any existing markers in the master clip are included with the clip when you add it to the Timeline or create a duplicate clip. However, if you open a clip from the Project window and add a marker to it, the marker won't be added to any duplicate clips or clip instances already in the Timeline.

When you add a marker to the Timeline or the Program view, it appears in both the Timeline and in the Program view, but is not added to any master clips. A marker you add to a clip in the Timeline appears with the clip, and a marker you add to the Timeline itself appears on the time ruler.

Timeline markers can also include a comment, a Web link, or a chapter link. Comments appear in the Program View window only, Web links initiate a jump to a Web page in your browser, and chapter links initiate a jump to a chapter in a QuickTime movie or DVD.

Premiere includes clip marker commands that you can use both to set the In and Out points of a clip and to go to those points. In addition, you can also set and go to the video/audio In and Out points, which is useful when you are working in a clip that includes a split edit. These commands are available only for the selected clip, and do not apply to the Timeline.

To add a marker:

- 1 Do one of the following:
 - To add a marker to a clip, open it in the Source view or the Clip window, or select a clip in the Timeline.
 - To add a marker to a clip in the Timeline, select the clip or double-click the clip to open it.
 - To add a marker to the Timeline, activate the Program view or the Timeline.

- 2 Go to the time location where you want to set the marker.
- 3 Choose Clip > Set Clip Marker or Timeline > Set Timeline Marker (depending on where you want to add the marker), and choose the marker you want to add.

Note: *If you are working in the Monitor window, you can use the Marker button (⏏) at the bottom of the window instead of using the menu command.*

Numbered markers that have been placed in the project are indicated in the menu by a dot to the left of the marker numbers.

 *To insert markers while a clip or the Timeline plays, play the clip and press * (the asterisk key) on the numeric keypad whenever you want to insert a marker. You can also insert a numbered marker by pressing its keyboard shortcut as a clip or the Timeline plays. (For keyboard shortcuts, see the Quick Reference Card.)*

To go to a marker:

- 1 Activate the window in which you want to go to a marker.
- 2 Do one of the following:
 - To go to a numbered marker, choose Clip > Go to Clip Marker > *marker x* or Timeline > Go to Timeline Marker > *marker x*.
 - To go to the next marker, choose Clip > Go to Clip Marker > Next or Timeline > Go to Timeline Marker > Next.
 - To go to the previous marker, choose Clip > Go to Clip Marker > Previous or Timeline > Go to Timeline Marker > Previous.
 - To go to the first marker in the Timeline, press Ctrl+Shift+Up arrow (Windows) or Command+Shift+Up arrow (Mac OS).
 - To go to the last marker in the Timeline, press Ctrl+Shift+Down arrow (Windows) or Command+Shift+Down arrow (Mac OS).

To use markers to help position clips, use the Snap to Edges command in the Timeline window menu or the Toggle Snap to Edges button (⏏) at the bottom of the Timeline window (see “Moving clips in time” on page 207). To hide markers or move them when moving multiple tracks, use the Show Markers and Block Move Markers options, respectively, in the Timeline Window Options dialog box (see “Customizing the Timeline window” on page 172).

To delete a marker:

- 1 Do one of the following:
 - To delete a marker from a clip, open it in the Source view or the Clip window, or select a clip in the Timeline.
 - To delete a marker from a clip in the Timeline, select the clip or double-click it to open it.
 - To delete a marker from the Timeline, activate the Program view or the Timeline.
- 2 Go to the marker you want to delete (see previous procedure).
- 3 Choose Clip > Clear Clip Marker > Current Marker or Timeline > Clear Timeline Marker > Current Marker, as appropriate.

To delete all markers:

- 1 Do one of the following:
 - To delete markers from a clip, open it in the Source view or the Clip window.
 - To delete markers from the Timeline but not from clips in the Timeline, activate the Program view or the Timeline.
- 2 Choose Clip > Clear Clip Marker > Clear All Markers or Timeline > Clear Timeline Marker > Clear All Markers.

Using Timeline markers for comments

You can add comments to a Timeline marker, and if you are in QuickTime Editing mode, the comments are displayed in the Monitor window as ghosted text. The default duration for marker comments is one frame (the frame where the marker appears on the Timeline), and the comment displays when that frame displays. To display the comment for longer than one frame, increase the comment duration.

To create a marker comment:

- 1 Activate the Program view or the Timeline.
- 2 Go to the time location where you want to add the link.
- 3 Click the Marker button () at the bottom of the Program view, choose Mark, and select a marker number.
- 4 When the marker appears in the Timeline, double-click it to open the Marker dialog box.

- 5 Type a comment in the Comment field.
- 6 Type a duration in the Duration field for the amount of time you want the comment to display.

Creating Web links

By typing a Uniform Resource Locator (URL) under Web Links in the Marker dialog box, you create an automatic link to that site at the marker's location in the program. Premiere embeds this information within movies. When these movies are included in Web pages created by programs such as Adobe GoLive, the embedded URL is recognized at playback, initiating a jump to the specified URL. You can further define the link by typing a specific frame number within the site for Target Frame. Web link markers work only with Timeline markers and supported output formats, such as QuickTime.

To create a Web link:

- 1 Create a Timeline marker and then double-click it to open the Marker dialog box.
- 2 For Web Links, type the URL for the site.
- 3 To activate a specific frame in a site, type the filename of the frame for Frame Target and click OK.

To view or modify information for a Web link:

- 1 Double-click a Timeline marker.
- 2 In the Marker dialog box, view the information and make any changes you want.
- 3 To view or change information for another marker, click Prev or Next. When you are done, click OK.

Creating chapter links

You can also create a Timeline marker as a chapter reference point, similar to chapters used in CD-ROM and DVD discs. Like the chapters of a book, a chapter link divides a movie into segments. Chapter links are supported in QuickTime movies and DVD.

To create a chapter link:

- 1 Create a Timeline marker and then double-click it to open the Marker dialog box.
- 2 For Chapter Links, type the chapter name and number and click OK.

Editing clips

The options in this section can be used on only one clip at a time, unless otherwise noted in the descriptions.

Editing a clip in its original application

The Edit Original command opens clips in their original application so that you can edit them and then have those changes automatically incorporated into the current project without exiting Premiere or replacing files. Exported Premiere movies can also be embedded with information that allows them to be opened using the Edit Original command that is in other applications, such as Adobe After Effects.

To edit a clip in its original application:

- 1 Select a clip in either the Project Window or the Source View of the Monitor Window.
- 2 Choose Edit > Edit Original.

To save a Premiere project with the information necessary to use the Edit Original command:

When exporting a clip or the Timeline, choose Project Link from the Embedding Options menu in the Export Settings dialog box. For information on exporting a movie, see “Exporting a video” on page 346.

Scaling a clip

When a clip is in the Timeline, you can scale and position it using the scaling options provided by the Motion feature. For information about the Motion feature, see “Animating a clip’s motion” on page 311.

To change the size of a clip and preserve its position:

- 1 Select a clip in the Timeline.
- 2 Choose Clip > Video Options > Motion.
- 3 In the Zoom option, drag the slider or type a scaling percentage. Watch the sample image in the upper right corner of the dialog box; ignore the motion preview in the upper left corner of the dialog box for now.
- 4 In the sample image with the motion path, drag the first (red) motion point to position the scaled clip in the frame.

- 5 Write down the coordinates in the Info option and the percentage in the Zoom option.
- 6 Click the second (white) motion point in the sample image, and type the Info coordinates and Zoom percentage that you noted in the previous step. This sets position and zoom to begin and end at the same point so that the clip does not move or scale over time.
- 7 Check the motion preview in the upper left corner of the dialog box. If the image is at the correct position and size, click OK. If not, repeat steps 4 through 6 to reposition the image.

Changing clip duration and speed

The *duration* of a video or audio clip is the length of time it plays—the difference in time between a clip’s In point and Out point. The initial duration of a clip is the same as it was when the clip was imported or captured. If you alter the beginning and ending of a clip by editing the source In and Out points, its duration changes. You can also set the duration of a clip by specifying a length of time from its current source In point. A still image can also have a duration if you want to display it for a specific length of time. You can set the default duration of the still images you import; see “Importing still images” on page 153.

The *speed* of a clip is the playback rate of the action or audio compared to the rate at which it was recorded. Speed is initially the same as it was when the clip was imported or captured. Changing a clip’s speed alters its source frame rate and may cause some frames to be omitted or repeated. In addition, changing the speed of a clip requires playing the same number of frames for a different length of time, which also changes the duration (moves the Out point) of the clip. Changing the speed to a negative value (such as -100) causes the clip to play in reverse. When you change the speed of a clip containing interlaced fields, you may need to adjust how Premiere treats the fields, especially when the speed drops below 100% of the original speed. See “Processing interlaced video fields” on page 193.


Note: *When playing back a reversed (negative speed) .AVI clip in Premiere for Windows, you cannot use the Loop or Play In to Out buttons in the Clip window or Source view.*

To change the duration of a clip or still frame:

- 1 In the Timeline or Project window, select a clip.
- 2 Do one of the following:
 - To change duration numerically, choose Clip > Duration, type a new duration, and click OK.

- To change duration visually in the Timeline, move the selection tool over the edge of the clip, and drag either end of the clip. If you are making the clip longer, the source clip must contain enough additional frames beyond its source In and Out point to accommodate the adjustment.

As you move the selection tool over the edit point between two clips, the icon changes, depending on which clip it is over and whether that clip has additional frames available.




The icon changes to show that it affects the left clip (A) or the right clip (B). The arrows indicate which way a clip can be trimmed: either left (C), right (D), or both directions (E).

To change the speed of a clip in the Timeline only:

1 Select a clip, and do one of the following:

- To change speed numerically, choose Clip > Speed. Type a percentage or new duration (or type a negative value to play a clip in reverse), and click OK.
- To change speed visually, select the rate stretch tool () and drag either end of the clip.



To change the speed of a clip that is not in the Timeline:

1 In a Project or Bin window, select a clip.

2 Do one of the following:

- To specify the new speed in terms of percentage or duration, choose Clip > Speed. Type a percentage or new duration (or type a negative value to play a clip in reverse), and click OK. Applying this command to a clip in a Project or Bin window won't affect clips already in the Timeline.

- To specify a new speed by changing the frame rate of the source clip, choose Clip > Advanced Options > Interpret Footage. Click Assume This Frame Rate, type a value in frames per second, and click OK. Premiere redistributes all of the clip's frames to create the new speed. If there are Timeline instances and duplicate clips based on the clip, their frame rates and durations change accordingly.

 *If you set a clip in the Timeline to the duration you require, but you don't like where the clip begins and ends in relation to the clips before and after it, you can use the slip tool to adjust the clip without changing the clip's program In and Out point or duration. See "Editing a clip that exists between other Timeline clips" on page 208.*

Changing the frame rate of a clip

You can change the number of frames displayed per second for a clip by specifying its frame rate. You may want to change the frame rate of a video file to decrease its frame size or make it match the rate of other clips in your project. Changing the frame rate does not change the speed of action, unless you use the Interpret Footage command, which changes both the frame rate and the speed of action. When you specify a frame rate lower than that at which the clip was shot or lower than the project frame rate, there aren't enough source clip frames to match the project frame rate, and movement may appear jerky. In this situation, Premiere makes up for the missing frames by repeating the last available source frame until the next new source frame is available. However, you can apply *frame blending*, which interpolates between available frames to create intermediate frames that can make motion seem smoother. Frame blending is also useful after changing clip speed, which also changes the frame rate.

The actual frame rate of a clip during playback or export depends on a complex relationship between the source clip frame rate, the project timebase, the frame rate you specified for playback or exporting, and any modifications you make using the procedures in this section. Changing the frame rate may cause some frames to be omitted, created, or repeated. If you want to change the frame rate for the entire Timeline, do not use any procedures in this section; instead, see "Video settings" on page 77 and "About exporting video from Premiere" on page 337.

To change the frame rate of a source clip in order to change the speed of action:

- 1 Select a clip in a Project or Bin window, or in the Timeline.
- 2 Choose Clip > Advanced Options > Interpret Footage.

3 Select Assume This Frame Rate, type a value in frames per second, and click OK. Premiere redistributes all of the source clip's frames to create the new speed. If there are Timeline instances and duplicate clips based on the clip, their frame rates and durations also change.

To change the frame rate of a clip in the Timeline without changing the speed of action:

- 1** Select a clip in the Timeline, and choose Clip > Video Options > Frame Hold.
- 2** In the Clip Frame Rate section, select Alternate Rate and type a new frame rate.
- 3** Select Frame Blending if desired, and click OK.

Processing interlaced video fields

In some video sources, such as NTSC, PAL, or SECAM, each video frame consists of two interlaced fields, each one representing a particular point in time. One field contains the odd-numbered lines in the frame, and the other contains the even-numbered lines. The two fields display in sequence to create a frame, but the *field dominance*, or the field displayed first, can vary depending on the video format and the equipment used to capture and play it. If the field dominance is reversed, motion may flicker or appear jerky because the fields no longer display chronologically. Fields can become reversed in the following situations:

- The field dominance of the original videotape was the opposite of the field dominance of the video-capture card used to capture the clip.
- The field dominance of the original videotape was the opposite of the field dominance of the video-editing or animation software that last rendered the clip.
- You have set an interlaced clip to play backward in Premiere.

Premiere can process fields for an interlaced clip in the Timeline so that the clip's picture and motion quality are preserved in situations such as changing the clip speed, exporting a filmstrip, playing a clip backwards, or freezing a video frame. The following settings operate on individual clips; final results are affected by the project settings in the Keyframe and Rendering Options (see the description of the Field Settings option in "Keyframe and rendering options" on page 80 and "Exporting a video" on page 346).

To specify field processing options for a clip:

- 1 Select a clip in the Timeline.
- 2 Choose Clip > Video Options > Field Options.
- 3 Select Reverse Field Dominance if the field dominance of the selected clip is the opposite of the field dominance used by your video-capture card. This option is also useful when your project contains clips captured using different video-capture cards or when you play a clip backward.
- 4 Click one of the following Processing Options:
 - Select None if you don't want to process source clip fields.
 - Select Interlace Consecutive Frames to convert pairs of progressive-scan (noninterlaced) frames into interlaced fields. This option is useful for converting 60-fps progressive-scan animations into 30-fps interlaced video, because many animation applications don't create interlaced frames.
 - Select Always Deinterlace if you want to convert interlaced fields into whole progressive-scan frames. Premiere deinterlaces by discarding one field and interpolating a new field based on the lines of the remaining field. It keeps the field specified in the Field Settings option (see "Keyframe and rendering options" on page 80 and "Exporting a video" on page 346). If you specified No Fields, Premiere keeps the Upper Field unless you selected Reverse Field Dominance, in which case it keeps the lower field. This option is useful when freezing a frame in the clip.
 - Select Flicker Removal to stop a small object in a picture from flickering, such as a one-pixel horizontal line. This option is sometimes known as *vertical convolution*, and can be useful with still images. If an object is as thin as a single scan line, it may appear only in one of the two video fields. This causes flicker because the object is drawn only as every other field appears. When you select Flicker Removal, Premiere blurs the two fields together slightly so that thin objects appear at least partially in both fields. The full resolution of the frame is preserved.
- 5 Select Deinterlace When Speed is Below 100% to automatically identify and retain fields that would best provide smooth-looking slow motion. Whether or not the upper or lower field in the successive frames is kept will depend on when that frame occurs. When you're done, click OK.

Maintaining the original aspect ratio of a clip

A project can contain clips that have varying aspect ratios (proportions of height to width). The aspect ratio of a project is determined by the frame size you specify in the Project Settings or Export Settings dialog boxes. When a clip in the Timeline uses an aspect ratio that is different from the project aspect ratio, Premiere stretches the clip to match the aspect ratio of your project. However, this distorts the picture; resolve this problem by maintaining the clip's original aspect ratio. When you maintain the aspect ratio of a clip with a different aspect ratio from the frame, two sides touch the edge of the frame and empty space appears outside the other two sides, similar to how letterboxed wide-screen videos appear on a television. You can specify the color for the empty areas.

To maintain the original aspect ratio of a clip:

Select a clip in the Timeline and choose Clip > Video Options > Maintain Aspect Ratio.

To set the color for frame areas outside a clip with a maintained aspect ratio:

- 1 Select a clip in the Timeline.
- 2 Choose Clip > Video Options > Aspect Fill Color, specify a color (see “Using the color picker” on page 290), and click OK.

Enabling and disabling clips

Disabled clips do not appear in the Monitor Program view and will not appear in a preview or video file that you export. You can disable clips in the Timeline. This is useful if you want to suppress clips while you try out a different editing idea, to shorten processing time when working on a complex project, or to exclude a clip from an EDL you export. If you have not locked a disabled clip, you can still make changes to it. If you want to disable all clips on the same track, exclude the entire track instead; see “Customizing track views” on page 173.

To enable or disable a clip:

Select one or more clips in the Timeline, and choose Clip > Enable Clip on Timeline. A check mark next to the command indicates that the selected clip is enabled. Disabled clips are marked by a hatch pattern of backslashes.

Locking and unlocking clips

Locking clips in the Timeline is useful for preventing changes to them—particularly accidental changes. Locked clips continue to be displayed in the Monitor Program view and will appear in video files you export. They appear in the Timeline with a hatch pattern of slashes. If you want to lock all clips on the same track, lock the entire track instead; see “Locking and unlocking tracks” on page 180.

To lock or unlock a clip:

Select one or more clips in the Timeline and choose Clip > Lock Clip on Timeline. A check mark next to the command indicates that the selected clips are locked.

Finding the source of a program clip

You can quickly find the source of any clip in the Timeline and highlight it in the Project or Bin window that stores it. You can also view the source of a clip in the Monitor window so that it is ready to edit.

To view the source of a program clip:

Select a clip in the Timeline and do one of the following:

- Choose Edit > Locate Clip to highlight the source in the window that stores it.
- Choose Clip > Open Clip to view the source in the Monitor window.

Freezing a video frame

You can freeze one frame of a clip, so that only that frame displays for the duration of the clip, as if you imported the frame as a still image. You can freeze on the clip’s In point, Out point, or at marker 0 (zero) if present.

To freeze a video frame:

- 1 Select a clip in the Timeline.
- 2 If you want to freeze a frame other than the In or Out point, move the edit line to the frame you want, and choose Clip > Set Clip Marker > 0.
- 3 Choose Clip > Video Options > Frame Hold.
- 4 Select Hold On, and select the frame you want to hold from the menu.

5 Specify the following options as necessary and then click OK:

- If one or more effects with keyframes are applied to the clip and you want to prevent clip settings from changing during the duration of the clip, select Hold Filters.
- If the clip was originally interlaced video, select Deinterlace to prevent a flickering image.

Note: If the frame doesn't freeze, make sure that you set the marker on a clip and not on the Timeline ruler.

Editing a video program

You can edit a program in the Monitor window using the source and program controllers to enter timecode, or you can edit visually in the Timeline. Some time-based edits are easier in the Timeline, where you can adjust In and Out points and duration by clicking and dragging. By zooming in on the Timeline, you can edit individual frames with the mouse. By zooming out, you can quickly make large changes (see “Using the Timeline window” on page 171).

Editing using the keyboard

Some experienced video editors can edit faster using the keyboard than the mouse. Premiere provides keyboard shortcuts for most commands and buttons, so it is possible to edit a video program with minimal use of the mouse. This *User Guide* documents only those keyboard shortcuts that have no equivalent in menus, tools, or buttons. Keyboard shortcuts are fully documented in the application and on the Quick Reference Card.

To find the keyboard shortcut for a command, tool, or button:

Do one of the following:

- For a tool or button, hold the pointer over a tool or button until its Tool Tip appears. If available, the keyboard shortcut appears in the Tool Tip after the tool description. (If Tool Tips do not appear, choose Edit > Preferences > General and Still Image and make sure that Show Tool Tips is selected.) Repeatedly press a timeline tool shortcut to cycle through all the tools available in the group.

- For a menu command, the keyboard shortcut is listed on the menu to the right of the command, if a shortcut is provided.
- For keyboard shortcuts not listed in menus or Tool Tips, see the Quick Reference Card.



Keyboard shortcuts are also listed in online Help.

Adding a clip to the Timeline

A clip in your project is not actually part of the final video program until you add it to the Timeline. When you do this, it appears in the Program view and in the Timeline, and the first frame of the clip is the In point that you set in the Source view. You can add or remove clips by clicking and dragging clips between windows or by using Monitor window controls. Dragging is a more visual method and depends heavily on using the mouse. Using the Monitor window controls emphasizes the keyboard and allows many edits to be performed entirely within the Monitor window. You can use either method at any time.


When you add clips to the Timeline by dragging, the clip is added to the track and time position where you drop it. However, when you add clips to the Timeline using Monitor window controls or by using the keyboard, Premiere cannot assume exactly how and where you want a clip to be added. In such a case, you must specify video and audio tracks in advance and, if desired, set In and Out points for the clip and/or the program.

***Note:** Depending on the relationship between your source clip and project settings, certain source frames may be omitted or repeated after the clip is added to the Timeline.*

To add a clip by dragging:

- 1** Mark the In and Out points of the source clip. (See “Marking and finding In and Out points” on page 180.)

2 Drag the clip from the Source view to an unused spot in the desired Timeline video or audio track. If you drag a clip that contains both video and audio, and if both Take icons are enabled (see “Specifying source and target tracks” on page 178), Premiere automatically adds both the video and audio and starts them at the same time.



 If you don't need to trim a clip or you don't want to trim it yet, drag it directly from a Project or Bin window to the Timeline.

Note: If you are building a rough cut and have expanded the Video 1 track, start by dragging clips into the Video 1A track. Use the Video 1B track as an alternate track, or B-roll, and use tracks Video 2 and above as superimpose tracks (see “Customizing track views” on page 173). Avoid using the Video 1A track to insert cutaways, or alternate footage, over the Video 1B track; instead, put cutaways in the appropriate superimpose track.

To add a track while adding a clip:

Drag a clip from the Project window or from the Source view in the Monitor window into the time ruler or into the blank space at the bottom of the Timeline window. Premiere adds either an audio track, video track, or both, depending on the content of the source clip.

To add a source clip using Monitor window controls:

- 1 Set up the Take Video and Take Audio icons and the target program tracks (see “Specifying source and target tracks” on page 178).
 - 2 Mark the In and Out points of the source clip (see “Marking and finding In and Out points” on page 180).
 - 3 Drag the program controller to the point in time where you want the source clip In point to begin playing. See “Using Monitor window controllers” on page 166.
 - 4 Do one of the following:
 - Click the Insert button () or choose Clip > Insert at Edit Line. Any video and audio clips following the edit point are moved later in time by the duration of the inserted source clip. If the edit line bisects an existing clip, Premiere splits the clip and moves the clip’s second half and any other subsequent clips later in time, to make enough room for the new clip. Note that the exact tracks that move depend on the setting of the On Insert option in the Timeline Window Options dialog box; see “Customizing the Timeline window” on page 172.
 - Click the Overlay button () or choose Clip > Overlay at Edit Line. Any existing video or audio frames occupying the duration of the inserted clip are replaced by the inserted clip.
- For information about editing clips in the program, see “Editing a clip that exists between other Timeline clips” on page 208.

Note: By default, the Insert and Overlay buttons add a clip to the Timeline at the edit line. You can override this and specify the intended location of your clip by setting a program In point, a program Out point, or both. See “Replacing program frames using a three- or four-point edit” on page 204.

Adding multiple clips using an automated process

To quickly assemble a rough cut of a project or add a sequence to an existing project, add multiple clips from a Project window bin to the Timeline using the Automate to Timeline command. Premiere uses an insert edit to add the clips. In A/B Editing mode, Premiere alternates the video clips between the Video 1A and Video 1B tracks and the audio clips between the Audio 1 and Audio 2 tracks. In Single-Track Editing mode, Premiere places all the video clips side by side on the Video 1 track and alternates the audio clips between Audio 1 and Audio 2 tracks. Premiere can also automatically add transitions. The Automate to Timeline command adds only the clips within the bin you are adding; it does not add other bins or the clips they contain that are within the bin you are adding.

In addition to using the Automate to Timeline command with a bin in the Project window, you can use it with the Storyboard window, which lets you organize clips by dragging them in the window. See “Creating a storyboard” on page 203.

Choosing Automate to Timeline displays the Automate to Timeline dialog box, which provides the following options:

Contents Specifies what part of the bin gets added to the Timeline. If you choose Whole Bin, all clips in the bin are added, regardless of whether you have selected clips. If you choose Selected Clips, only those clips you have selected are added.

Ordering Specifies the method used to determine the order of the clips when they are added to the Timeline. If you choose Sort Order, Premiere uses the sort order set in the list view of the Project window, regardless of which view is currently selected. (If you are working in the Storyboard window, Sort Order uses the order in which the clips appear in the window, from left to right and from top to bottom.) If you choose Selection Order, clips are added according to the order in which you selected them in the Project window.

***Note:** When the Project window is in Icon view, you can select clips by dragging a selection marquee around them. If you use this method to select clips and Ordering is set to Selection Order, Premiere will add the clips using the order in which they appear in the Project window.*

Placement Specifies how clips are placed in the Timeline. If you choose Sequentially, clips are placed in sequence, alternating between the Video 1A and 1B tracks in A/B Editing mode, or side by side in Single-Track Editing mode, with the audio portions alternating between the Audio 1 and Audio 2 tracks. If you choose At Unnumbered Markers, clips are placed at unnumbered Timeline markers. Your choice for Placement determines which of the following options display in the Automate to Timeline dialog box.

Insert At Specifies where in the Timeline the first clip is added. You can choose to add clips at the beginning of the Timeline, at the current position of the edit line, or at the end of the Timeline.

Insufficient Material Specifies how Premiere handles the space between clips when clips are added based on markers and a clip's duration leaves a space between it and the next clip. Choose Fit to Fill to change the duration of the clip to fill the space between markers. Choose Leave Gap to leave the space blank. Insufficient Material is available only when At Unnumbered Markers is selected for Placement.

Clip Overlap Specifies the overlap between adjacent clips in the Timeline. You can set this option to either frames or seconds. The default value of this option is 15 frames. By typing a negative number, you can create a gap between adjacent clips. Clip Overlap is available only when Sequentially is selected for Placement.

Use Default Transition When selected, places the default transition (defined in the Transitions palette) in each overlap between the clips in the Video 1A and Video 1B tracks in A/B Editing mode, or between the clips on the Video 1 track in Single-Track Editing mode. This option is not available if Clip Overlap is set to 0. This option is selected by default. Use Default Transition is available only when Sequentially is selected for Placement.

Perform Audio Cross Fade When selected, creates an audio cross-fade between all overlapping audio clips on the Audio 1 and Audio 2 tracks. This option is not available if Clip Overlap is set to 0. This option is selected by default. Perform Audio Cross Fade is available only when Sequentially is selected for Placement.

Ignore Audio When selected, ignores the audio in clips selected to be automated to the timeline.


To add multiple clips to the Timeline:

- 1 Assemble the clips you want to add by dragging them into a bin in the Project window.
- 2 If you want to add only some of the clips in the Project window, select them either by shift-clicking them or by dragging a selection marquee around them in Icon View.
- 3 Choose Automate to Timeline from the Project window menu.
- 4 Choose the appropriate options in the Automate to Timeline dialog box and then click OK.

Creating a storyboard

To specify and organize the individual shots for a film or video, editors create a *storyboard*, which is a collection of sketches, descriptions, or both, laid out in order. In a similar way, you can organize a set of clips in a window and then move these clips into the Timeline window to create a rough cut.

In the Storyboard window, clips are represented by icons, similar to those displayed in the Project window when Icon View is selected. Each icon displays the same poster frame shown in the Project window, which you can change. See “Customizing a Project or Bin window display” on page 94. You can select from four sizes for the icons. Each icon is assigned a number, indicating its order in the sequence. (This number is displayed only in the two largest icon sizes. Other information is included in the icons, depending on the size you select. The clip’s duration is shown only in the three largest sizes, and comments entered in the Project window are shown only in the two largest sizes.) The Storyboard window adds arrows from one icon to the next to show the sequence, and also shows an end marker on the last icon.



*A. The poster frame B. A number to show sequence C. The filename
D. The duration E. Comments F. Arrows to show flow G. An end marker*

In addition to moving a sequence of clips from the Storyboard window to the Timeline window, you can move a sequence from a bin to the Timeline (see “Adding multiple clips using an automated process” on page 201). You can also print a sequence to video or export it to tape (see “About exporting video from Premiere” on page 337).

To create a storyboard:

- 1 Choose File > New > Storyboard.

2 Import clips into the Storyboard window using one of the following methods:

- If a Project or Bin window is open and contains clips, drag the clips you want into the Storyboard window.
- Choose File > Import and choose a command from the Import menu. Locate and select the files or folder you want to import, and click OK.

3 In the Storyboard window, drag the clips to arrange them in the order you want. If you want to relocate a clip earlier in the sequence, drag it to the clip you want it to precede. If you want to relocate a clip later in the sequence, drag it to the clip you want it to follow.

4 If you want to include only certain clips, Ctrl-click (Windows) or Shift-click (Mac OS) the clips to select them.

5 Choose File > Save As, specify a location and filename, and click OK.

6 Click the Automate to Timeline button (⇨) at the bottom of the Storyboard window.

7 For Contents in the Automate to Timeline dialog box, choose Whole Bin to transfer all clips, or choose Selected Clips if you want only the clips you selected.

8 For Insert At, choose the insert point and type a different value for Clip Overlap, if desired, or type 0 for no overlap.

9 Select Use Default Transition if you want Premiere to add transitions between clips, and select Perform Audio Cross Fade if you want audio fades added. Click OK.

To change the icon size:

1 In the Storyboard window menu, choose Storyboard Window Options.

2 Select the icon size you want, and click OK.

Replacing program frames using a three- or four-point edit

In the Monitor window, you can replace a range of program frames with a range of source clip frames. Premiere provides three-point and four-point edits, standard techniques in traditional video editing.

In a *three-point edit*, for the source and program together, you mark either two In points and one Out point, or two Out points and one In point. This type of edit is useful when one end point of source material or program material is critical but the other is not. When you add the source frames to the Timeline, Premiere determines the fourth point by applying the duration of the In and Out points you specified to the third point. For

example, if you mark a source In point of 00:03:15, a source Out point of 00:04:15, and a program Out point of 13:22:05, Premiere applies the 1-second duration between the source In and Out points to the program Out point, and automatically sets the program In point to 13:21:05. You can leave any single In or Out point unmarked, but you must specify a total of three In and Out points.

In a *four-point* edit, you mark source In and Out points and program In and Out points. A four-point edit is useful when the starting and ending frame in both the source and program are critical. If the marked source and program durations are different, Premiere alerts you to the discrepancy and provides alternatives to resolve it.

You can preview three- or four-point edits by synchronizing the source and program controllers. See “Previewing an edit by synchronizing controllers” on page 231.

To perform a three-point edit:

- 1 Set up the Take Video and Take Audio icons and the target program tracks (see “Specifying source and target tracks” on page 178).
- 2 In the Source and Program views, mark any combination of three In and Out points (see “Marking and finding In and Out points” on page 180).
- 3 Click the Insert button () or the Overlay button (.

To perform a four-point edit:

- 1 Set up the Take Video and Take Audio icons and the target program tracks (see “Specifying source and target tracks” on page 178).
- 2 Using the Source controller, mark an In point and an Out point for the source clip. Then use the Program controller to mark an In point and Out point for the program. (See “Marking and finding In and Out points” on page 180.)
- 3 Click the Insert button () or the Overlay button (). If the marked source and program durations are different, select one of these options when prompted:
 - Change Speed distributes the range of source frames within the program In and Out points you specified, even though their durations are different. This causes the clip to play faster or slower.
 - Trim Source moves the source Out point you specified until the source frames fit within the program In and Out points you specified. The speed of the clip will not change.
 - Cancel Edit applies no changes.


Selecting clips

When you want to perform an action that affects a clip as a whole, such as applying an effect, deleting a clip, or moving a clip in time, first select the clip in the Timeline. The toolbox contains selection tools that can handle various selection tasks.

To select one or more clips:

Do any of the following:


- To select a single clip, select the selection tool (⬆) and click a clip in the Timeline.
- To select multiple clips by dragging, select the range select tool (⌈⌋) and drag a rectangle that includes any part of the unlocked clips you want to select.



- To select multiple clips by clicking, select the range select tool (⌈⌋) or the selection tool and hold down Shift as you click each clip you want to select. The range select tool selects clips in groups and the selection tool selects each adjacent clip or all clips between a previous selection and the current one. To use the selection tool to select or deselect individual clips in varying places in the timeline, hold down Command (Mac OS) or Ctrl (Windows) as you click the clip you want to select or omit.
- To select all whole or partial clips that exist on and after a certain time on *one* track, select the track select tool (⌈⌋) and click the clip at the beginning of the time span you want to select. Press Shift as you click to select clips on additional tracks.



- To select all whole or partial clips that exist on and after a certain time on *all* tracks, select the multitrack select tool (⌘) and click the clip at the beginning of the time span you want to select.



- To select a linked video clip or audio clip to edit independently of its partner, click the Toggle Sync Mode button (≡) at the bottom of the Timeline window to turn off Sync mode (Sync mode is off when there is no link icon visible in the Toggle Sync Mode button), and then edit the clip. When you are finished editing, click the Toggle Sync Mode button again to restore Sync mode.

Moving clips in time

In general, moving a clip is as simple as dragging it to any empty track area in the Timeline. A clip can snap to the edge of another clip, to a marker, to the start and end of the Timeline, or to the edit line.

To move a clip to a point earlier or later in the program:

Drag the clip to the left or right, position the clip by watching the In point and Out point indicator lines (if you stay on the same track) or the black rectangle that represents the clip duration (if you drag to a different track), and then release the mouse button.

Note: *If you have Sync mode turned on (for more information on Sync mode, see “Linking video and audio clips in the Timeline” on page 217) and you drag a clip containing both video and audio, Premiere attempts to keep video and audio on similar tracks. For example, if you drag a clip on track Video 3, Premiere will drag the clip’s audio along on Audio 3. If you try to drag the video part of the clip to a time where the track Video 3 is empty and Audio 3 is occupied, Premiere will move the audio clip to the next empty audio track at that time so that you can complete the drag. If there is no empty audio track at that time, Premiere will not allow the move.*

To snap the edge of a clip to the edge of another clip or a marker:

- 1 Make sure that Snap to Edges is selected in the Timeline window menu. If it isn't selected, choose it in the Timeline window menu, or click the Toggle Snap to Edges button (⌘⌥) at the bottom of the Timeline window.
- 2 Drag the edge of a clip close to the edge of another clip or a marker.

To snap a marker as you drag the clip that contains it:


- 1 Make sure that Snap to Edges is selected in the Timeline window menu. If it isn't selected, choose it in the Timeline window menu, or click the Toggle Snap to Edges button (⌘⌥) at the bottom of the Timeline window.
- 2 With the selection tool selected (⬅), position the pointer over the marker inside the clip you want to move. The pointer changes to a blue arrow.
- 3 As the blue arrow appears, drag the marker to the edge of another clip, a marker, or the edit line. As you drag, the blue arrow changes to a grabber hand, and the marker you're dragging snaps to other clip edges, markers, or the edit line.

Editing a clip that exists between other Timeline clips

Before you edit a clip in the Timeline, decide how you want to affect adjacent clips and the duration of the entire program. For example, when you make a clip shorter by moving its Out point to an earlier time, do you want all the following clips to stay in place or to fill the gap left by the clip you're adjusting? You specify exactly what happens to clips adjacent to the clip you want to adjust, making it easier to edit right the first time and preserve the integrity of the rest of the video program.


Premiere supports the following edits for a clip and the clips adjacent to it:

- A *rolling edit* keeps the program duration constant, and also maintains the combined duration of the two clips you are editing. You adjust the edit line, and the frames you add to or subtract from one clip are subtracted from or added to the clip on the other side of the edit line. To make an L-cut, turn off Sync mode before performing a rolling edit.




In this rolling edit, the edit line is dragged earlier in time—shortening the previous clip, lengthening the next clip, and maintaining the program duration.

- A *ripple edit* maintains the durations of all other clips by changing the program duration. You drag the edit line, and the overall program duration is lengthened or shortened by the number of frames you added to or subtracted from the clip you are editing. An empty space on one side of the edit point is treated as a clip and is adjusted by the ripple edit tool just as a clip would be. A ripple edit obeys the Shift Material in All Tracks and Shift Material Only in Target Tracks options in the Timeline Window Options dialog box, as well as the Sync mode setting.




In this ripple edit, the edit line is dragged earlier in time—shortening the preceding clip and the total program duration.

- A *slip edit* shifts the starting and ending frames of a clip forward or backward without affecting anything else in the Timeline. You drag a clip left or right, and its source In and Out points shift accordingly. The program duration and the source and program In and Out points of all other clips remain unchanged. The slip tool does not require there to be a clip on either side of the clip you are adjusting.



In this slip edit, a clip is dragged left, moving its source In and Out points earlier in time.

- A *slide edit* preserves the duration of a clip and the program duration by changing the In and Out points of the preceding and following clips. As you drag a clip left or right, the Out point of the preceding clip, the In point of the following clip, and the clip's program In and Out points are moved by the number of frames you moved the clip. The clip's source In and Out points and the program duration remain unchanged. The slide tool requires there to be a clip on either side of the clip you are adjusting.




In this slide edit, a clip is dragged left so that it starts earlier in the program, shortening the preceding clip and lengthening the following clip.


Note: When you perform any action that extends the duration of a clip, additional frames must be available in the clip's source (master) clip beyond the current In or Out point. For example, if you didn't trim the beginning or ending of a source clip before adding it to the Timeline, the clip is already using all frames available from its source, so its duration cannot be extended.

To perform a rolling edit:

- 1 Select the rolling edit tool (⏮⏭).




- 2 Position the rolling edit tool on the edge of the clip you want to change, and drag left or right. If Sync mode is off, the arrowheads on the rolling edit tool are thin and detached from their shaft, indicating that you are editing only the video or audio portion of a linked clip. The same number of frames added to the clip are trimmed from the adjacent clip.




Timeline during (left) and after (right) a rolling edit

To perform a ripple edit:

- 1 Select the ripple edit tool (⚡).




- 2 Position the ripple edit tool on the In or Out point of the clip you want to change, and drag left or right. The program duration is extended or shortened to compensate for your edit, but the duration of adjacent clips remains unchanged. When a clip has no additional frames available, the arrowhead on the ripple edit tool pointing to that clip is not visible. If Sync mode is off, the arrowhead on the ripple edit tool is white, indicating that you are editing only the video or audio portion of a linked clip.



Timeline during (left) and after (right) a ripple edit

To perform a slip edit:

- 1 Select the slip tool ()




- 2 Position the pointer on the video clip you want to adjust, and do one of the following:

- Drag left to move the source In and Out points earlier in the clip. This creates new Timeline In and Out points that reflect footage appearing later in the source clip.
- Drag right to move the source In and Out points later in the clip. This creates new Timeline In and Out points that reflect footage appearing earlier in the source clip.

Premiere updates the source In and Out points for the clip, displaying the result in the Monitor window and maintaining the clip and program duration.

To perform a slide edit:

- 1 Select the slide tool ()



- 2 Position the pointer on the video clip you want to adjust, and do one of the following:

- Drag left to move the Out point of the preceding clip and the In point of the following clip earlier in time.
- Drag right to move the Out point of the preceding clip and the In point of the following clip later in time.

When you release the mouse button, Premiere updates the In and Out points for the adjacent clips, displaying the result in the Monitor window and maintaining the clip and program duration. The only change to the clip you moved is its position in the Timeline.

Note: You can't use the slip and slide tools directly on audio clips, but when you use the slip and slide tools on video clips, any linked audio clips will be adjusted to match the video.

Splitting a clip

You can split a clip in the Timeline by using the razor tool (). Splitting a clip creates a new and separate instance of the original clip. It can be useful when you want to use different effects that can't both be applied to a single clip, such as different clip frame rates. When you split a clip, Premiere creates a new instance of the clip and any clips to which it is linked. If Sync mode is off, Premiere splits only the audio or video portion of linked clips.

***Note:** If you want to change effect settings over time, you needn't split the clip; you can apply keyframes to a single clip instead. See "Understanding keyframes" on page 323.*


To split a clip:

Do one of the following:

- Position the edit line where you want to split a clip and choose Edit > Razor at Edit Line.
- Select the razor tool () and click a clip in the Timeline where you want to split it.

To split multiple tracks at the same point in the Timeline:

Select the multirazor tool () and click a clip in the Timeline at the point where you want to split it. Premiere splits all unlocked clips on any unlocked track at that time point into two independent instances in the program.



Cutting and pasting clips and clip settings

You can rearrange existing clips in the Timeline by cutting and pasting. If you simply paste a clip, Premiere inserts it at a selected area in the Timeline by either trimming the clip's Out point to allow it to fit into a gap between two other clips or placing the entire clip. If you want another result, you can control exactly what happens to the clips at the edit point when you paste. This kind of control is most useful when you are pasting a clip of one duration into a selected space of a different duration.

If you have applied settings to a clip and want to use the same settings in another clip, you can easily copy the settings. For example, you might want to apply identical color correction to a series of clips captured in the same session.

To make a clip fit into a selected space when you paste it:

- 1 Select a clip and choose Edit > Copy.
- 2 Select an empty segment in the Timeline.
- 3 Choose Edit > Paste to Fit.
- 4 Click one of the following options:
 - Click Change Speed to either slow down or speed up the clip to fit it into the designated space.
 - Click Trim Source to adjust the duration to fit by keeping the source In point and setting a new source Out point.

To control how a clip pastes into a selected space:

- 1 Select a clip and choose Edit > Copy.
- 2 Select an empty segment in the Timeline.
- 3 Choose Edit > Paste Attributes, and make sure that Content is selected.
- 4 Select an option from the menu. An animated representation of the option appears in the Content section to help you determine if the selected option is appropriate.
- 5 Click Paste.

To transfer clip settings to another clip:

- 1 Select a clip to which effects, fade control, transparency, or motion has been applied in Premiere, and choose Edit > Copy.
- 2 Select a clip in the Timeline.
- 3 Choose Edit > Paste Attributes.
- 4 Click Settings and select the applicable settings you want to paste.
- 5 Click Paste.

Deleting space between clips

Quickly delete empty space between clips on a track using the Ripple Delete command.

To delete empty space between clips:

Select the empty space, and choose Timeline > Ripple Delete. Once the space is deleted, all clips on the track shift to close the gap.

Removing a clip or a range of frames from the program

You can remove an entire clip or a range of frames from the Timeline in two ways:

- *Lifting* removes frames from the program and leaves a gap of the same duration as the frames you remove.
- *Extracting* removes frames from the program and closes the resulting gap by ripple deletion.

These methods are most useful when you want to remove frames from the middle of a clip or across multiple clips on the same track. If you just want to remove frames from one end of a clip, simply trim the end of the clip (see “Editing a clip that exists between other Timeline clips” on page 208).

To remove frames without affecting other clips (lift):

Do one of the following:

- To remove an entire clip, select the clip in the Timeline and press the Delete key.
- To remove a range of frames, use the program controller to specify the In and Out points to remove, and click the Lift button () in the Monitor window.


To remove frames and close the resulting gap (extract):

Do one of the following:

- To remove an entire clip, select the clip in the Timeline and choose Timeline > Ripple Delete.
- To remove a range of frames, use the program controller to specify the In and Out points to remove, and click the Extract button () in the Monitor window.

To delete all clips on one track:

- 1 Select the track select tool ()



- 2 Click the first clip in the track, and press Delete.

Note: You can also delete a track; see “Adding, naming, and deleting tracks” on page 177.

Linking video and audio clips in the Timeline

When you add a clip containing video and audio to the program, and you’ve specified adding both the video and audio portions (see “Specifying source and target tracks” on page 178), the video portion appears in a video track and the audio portion appears in an audio track. The video and audio portions of the clip are *linked* so that when you drag the video portion in the Timeline, the linked audio moves with it. If you split the clip, the video and audio are still linked within the two resulting clips. You can link video only to audio—you cannot link a video clip to another video clip.

In many situations it is useful to link or unlink clips manually. For example, you might want to move previously unlinked audio or video clips together, or edit the In or Out point of the video or audio portion of a clip independently. You don’t have to unlink clips if you only want to delete one clip or the other.

When you want to work with linked clips individually, temporarily turn off synchronized behavior by using the Toggle Sync Mode button. When Sync mode is on, both clips of a linked pair behave as a single unit. In this mode, all Timeline tools act on both clips in a linked pair, and both clips are affected when you select, trim, split, delete, move, nudge, or


change the duration or speed of either clip. When Sync mode is off, linked clips can be edited independently, as if they were not linked. Premiere keeps track of sync information, even when Sync mode is turned off. When linked clips are moved out of sync, both clips display a red triangle at the In point to indicate the out-of-sync condition.

Note: The On Insert options in the Timeline Window Options dialog box control how clips are shifted along the Timeline, regardless of the Sync mode setting. If Shift Material in All Tracks is selected in the Timeline Window Options dialog box, all tracks are rippled in response to an edit. If Shift Material Only in Target Tracks is selected, only clips in target tracks are moved, which could offset the sync of linked clips, depending on which tracks were selected as target tracks. It is useful to remember that Sync mode specifies which portion of a clip is edited, and the On Insert options specify which clips are shifted in response to an edit.

The video and audio portions of linked clips are both light green so you can easily see that they are linked.

To link video and audio:

Select the link/unlink tool (🔗), click the first clip you want to link, and then click the second clip you want to link.



To unlink video and audio:

Do one of the following:

- Select a linked clip and choose Clip > Unlink Audio and Video. A white marker is added to each unlinked clip. If you wish to realign these clips after they are moved independently, drag this marker to the accompanying clip's marker.
- Select the link/unlink tool (🔗), click the first clip you want to unlink, and then click the second clip you want to unlink.

To relink clips that were moved out of sync:

- 1 Click and hold the red triangle that appears at the In point of the out-of-sync clip. A box appears displaying the amount of time the clip is out of sync with its accompanying video or audio clip.
- 2 Drag inside the box and release the mouse button.

To edit linked clips individually:

Click the Toggle Sync Mode button (≡) to turn off Sync mode and edit a linked clip using Timeline tools. When you are finished editing the clip, click the Toggle Sync Mode button again to restore Sync mode.

Using the Trim view

The Monitor window Trim view is a precise way to trim clips interactively in any video track. You can perform ripple or rolling edits at any edit along the Timeline. As you make adjustments, you see the frames on both sides of the edit. You can also set a range of frames you see on both sides of the edit to expand your view of the context of the edit. The Timeline updates as you perform the edit.

When you're not in Trim view, the left monitor displays source clips and the right monitor displays the program. When you use the Trim view, both monitors represent clips in the program—the left monitor is the clip to the left of the edit line, and the right monitor is the clip to the right of the edit line.

***Note:** When you perform any action that requires moving a clip's In or Out point outward, such as adding frames in the Trim view, additional frames must be available in the clip's source (master) clip beyond the current In or Out point. For example, if you didn't trim the beginning or ending of a source clip before adding it to the Timeline, the edit line may already be at the first or last frame available from the source, so you will not be able to move its In or Out point any further out.*

To switch to Trim view:

Click the Trim Mode button (≡) at the top of the Monitor window. You can also choose Trim Mode from the Monitor window menu.

To find the edit you want to trim:

- 1 Select the target tracks in the Target drop-down menu.
- 2 Click the Previous Edit (⏮) or Next Edit (⏭) buttons. The frames on either side of the new edit line position appear in the Monitor Trim view.

To perform a ripple edit using Trim view:

- 1 Click the left or right view to activate the clip you want to trim. The respective active clip is indicated both by green timecode numbers and the depressed Set Focus Left or Set Focus Right buttons.

- 2 Do any combination of the following:

- To remove one frame from the left clip when it is active, or add one frame to the clip on the right when it is active, click the Trim Left button (-1). To edit multiple frames, click the Trim Left *n* Frames button (-5).
- To add one frame to the clip on the left when it is active, or remove one frame from the clip on the right when it is active, click the Trim Right button (+1). To edit multiple frames, click the Trim Right *n* Frames button (+5).

Note: You can set the number of frames edited by the Trim Left *n* Frames or Trim Right *n* Frames buttons (see the procedure “To set Trim view options” later in this section).

- To perform a ripple edit numerically, type a negative number (to move left) or a positive number (to move right) in the space between the buttons, and press Enter (Windows) or Return (Mac OS).
- To perform an interactive ripple edit, drag the jog tread for the left or right clip, or drag to the left or the right in either Trim view image once the corresponding ripple edit tool (⏮) or (⏭) appears in the respective image.

To perform a rolling edit using Trim view:

- 1 Click the Set Focus Both button (⏮⏭) or click in the space between the clip windows to activate both the clips to the left and right of the edit line.

2 Do any of the following:

- To remove one frame from the left clip and add one frame to the clip on the right, click the Trim Left button (). To edit multiple frames, click the Trim Left *n* Frames button (.
- To add one frame to the left clip and remove one frame from the clip on the right, click the Trim Right button (). To edit multiple frames, click the Trim Right *n* Frames button (.

Note: You can set the number of frames edited by the Trim Left *n* Frames or Trim Right *n* Frames buttons (see the procedure “To set Trim view options” later in this section).

- To perform a rolling edit numerically, type a negative number (to move left) or a positive number (to move right) in the space between the buttons, and press Enter (Windows) or Return (Mac OS).
- To perform an interactive rolling edit, drag left or right in the empty space between the two views.

To cancel an edit:

Click the Cancel Edit () button.

To preview the edit:

Click the Play Edit button (.

To return to the Source/Program view:

Click the Dual View button () at the top of the Monitor window.

To set Trim view options:

- 1** In the Monitor window menu, choose Monitor Window Options.
- 2** In the Trim Mode Options section, select one of the following options:
 - Click the first view option to display the frame to the left of the *tail* (the clip to the left of the edit line) and the frame to the right of the *head* (the clip to the right of the edit line).
 - Click the second view option to display the tail of the left clip with small representations of the frames before and after the tail, and the head of the right clip with small representations of the frames before and after the head.

- Click the third view option to display—from top to bottom—small representations of the fifth and first frames before the tail of the left clip or the head of the right clip, a large representation of the tail or the head, and small representations of the first and fifth frames after the tail or head.

3 For Large Frame Offset, specify the number of frames that will be trimmed when you use the multiple-frame trim buttons ([**-5**] or [**+5**]) that trim five frames by default.


4 Select Play Previews at Maximum Size when the program frame size is smaller than the available space in the Monitor window and you want trim previews to appear at the largest size that fits in the Monitor window. Then click OK.

Nesting edits using virtual clips


A *virtual clip* is like a second video program that you create in the Timeline, separate from the main video program. Like the main program, a virtual clip can contain multiple clips, transitions, and effects, and can span multiple tracks. Once a virtual clip is defined, you can use it in the main program any number of times. Premiere treats and represents a virtual clip as a single clip, and you can edit and apply settings to a virtual clip as you can with a source video clip. By using virtual clips to organize and group sequences, you can save time editing complex video programs. Using virtual clips, you can do the following:

- Reuse anything you build. For example, if you create a short sequence involving four superimposed video tracks and three mixed audio tracks, and you want to use the sequence ten times in a project, just build the sequence once, create a virtual clip from it, and add ten instances of the virtual clip to the Timeline.
- Apply different settings to copies of a sequence. For example, if you want a sequence to play back repeatedly but with a different effect each time, you can create a virtual clip and copy that for each instance where you want it to appear with a different effect.
- Update identical scattered sequences all at once. For example, if you create the virtual clip described in the first example and use the virtual clip in your video program ten times, you can simultaneously update all ten instances of the virtual clip just by editing the clips in the area of the Timeline that defines the virtual clip. And if different effects are applied to each instance of a virtual clip, the different effects are preserved for each instance. If you had copied and pasted the sequence instead of creating a virtual clip, you'd have to update one sequence and then copy and paste the update nine times, or edit each copy individually.

- Apply settings more than once to the same clip. For example, certain effects can be achieved only by combining transitions. However, you cannot apply more than one transition to the same point in time—unless you use a virtual clip. For example, you can apply a transition between two clips in the Timeline outside the main program, create two virtual clips using the clips on either side of that transition, and move the new virtual clips to the Timeline. The first transition you applied is now inside each virtual clip, so now you can apply a second transition between the two virtual clips.



Copying and pasting a sequence multiple times in the Timeline creates many objects in the Timeline.



Virtual clips achieve the same goal in a much simpler way.


When creating virtual clips, keep in mind the following:

- A virtual clip always represents the current state of the original Timeline area on which it is based, so if you edit that original area in any way, you will affect the virtual clips based there.
- Because the clips in a virtual clip must be on the Timeline but outside of the main video program, it's a good idea to create virtual clips in an area you set aside before the main program starts in the Timeline. This reduces the possibility that edits to the main program (such as ripple edits) will accidentally alter Timeline areas containing virtual clips. You can protect the original clips further by building virtual clips on tracks other than the ones containing the main program or superimpositions and by locking the clips or their tracks (see “Locking and unlocking tracks” on page 180 or “Locking and unlocking clips” on page 196).

- A virtual clip can contain one or more virtual clips. This technique, called *nesting*, can be useful when you are organizing a complex hierarchy of effects. You can nest up to 64 levels of virtual clips.
- Because virtual clips can contain references to many clips, actions involving a virtual clip may require additional processing time as Premiere applies the actions to all component clips.
- Because any changes you make to the source clips in a virtual clip alter the resulting virtual clip, you cannot place a virtual clip above, below, or before its source clips in the Timeline window. If you do, Premiere will be unable to create a preview file and the Program view will display either a black screen or yellow and black lines.


To create a virtual clip:

- 1 Drag the work area markers to mark the beginning and end of the main program (see “Previewing a video program” on page 227). Because you are about to create a second program within the Timeline, setting the work area to the main program helps ensure that when the program is finished, you export only the main program and not other areas of the Timeline.
- 2 In an area of the Timeline outside the main program work area, add and edit the clips you want in your virtual clip. Apply any effects and transitions if desired.
- 3 Select the block select tool ()



- 4 Drag to create a rectangle that defines the time boundaries of the clips you want to include in the virtual clip. You can include parts of clips; Premiere will use only the portions of clips inside the rectangle you drag.
- 5 Position the block select tool anywhere inside the rectangle. The pointer changes to the virtual clip tool ()

6 Drag the selected block to any other available location in the Timeline. You can also use only the audio or video portions of the source clips by holding down Shift as you drag either the audio or video portions of the clips you want to include in the virtual clip. As you drag, the virtual clip is represented by a black rectangle identical to the one you see when you drag a source clip.



Dragging to select an area to include in a virtual clip (left), and dragging the selection to create a virtual clip (right)

To locate the original frames that make up a virtual clip:

Do one of the following:

- In the Timeline, double-click the virtual clip.
- In the Timeline, select the virtual clip and then choose Edit > Locate Clip.

The Timeline displays the selection rectangle around the source frames for the virtual clip.

 *Change the area in the Timeline that is the source for a virtual clip by dragging the edge of the virtual clip. You can observe the difference if you double-click the virtual clip before and after you trim it.*

Creating a counting leader

A counting leader helps a projectionist verify that audio and video are working properly and are synchronized. You can create and customize a *universal counting leader* to add to the beginning of a project. The leader is 11 seconds long, so you may want to account for that duration as you plan to add it to the Timeline.

To create a leader:

Click the Create Item button at the bottom of the Project Window and choose Universal Counting Leader from the Create Type menu. Specify the following options as needed:

Wipe Color Click to specify a color for the circular one-second wipe area, and click OK.

Background Color Click to specify a color for the area behind the wipe color, and click OK.

Line Color Click to specify a color for the horizontal and vertical lines, and click OK.

Target Color Click to specify a color for the double circles around the numeral, and click OK.

Numeral Color Click to specify a color for the countdown numeral, and click OK.

Cue Blip on Out Select to display a small cue circle in the last frame of the leader.

Cue Blip on 2 Select to play a beep at the two-second mark.

Cue Blip at All Second Starts Select to play a beep at the beginning of every second during the leader.



You can customize a counting leader by double-clicking the leader and modifying the options.

Creating color bars and a 1-kHz tone

Editors place color bars at the beginning of their programs to help a viewer calibrate the video monitor that will show the program. A 1-kHz tone is usually recorded underneath the color bars and is used to help calibrate the audio. You can create a single clip containing both color bars and a 1-kHz tone; this clip is 10 seconds long.

To create color bars and a 1-kHz tone:

Click the Create Item button at the bottom of the Project Window and choose Bars and Tone from the Create Type menu.

Creating black video

You can create a clip of black video to insert in any section of your program. The black video clip is a 640 x 480 still image with a duration of four seconds. Adjust the duration by dragging either edge of the clip. To insert a clip of a different color, use a color matte. See “Adding a background matte” on page 306 for steps on how to create a color matte.

To create black video:

Click the Create Item button at the bottom of the Project Window and choose Black Video from the Create Type menu.

Previewing a video program

You can preview part or all of the video program as you edit it without having to export the entire video program. You can display previews in the Monitor Program view, in the center of a monitor on a black background, or on any compatible NTSC or PAL monitor attached to your computer. Previewing is relatively quick for a program that simply cuts between clips. Applying transitions, effects, or superimposition settings adds processing time to a preview.

Premiere offers several methods to preview your program; the method you choose depends on whether you want a quick preview, a preview at a precise frame rate, or a compromise between the two. The appearance of a preview is controlled by the settings in the Video Settings panel of the Project Settings dialog box (see “Specifying project settings” on page 74).


The area to be previewed, called the Work Area, is defined by a yellow bar that stretches across the top of the timeline, or the work area band. The work area bar automatically expands to encompass the whole program as you add clips to the timeline, but it is also manually adjustable.

When you use certain video cards, you can view in real time programs that include transitions, motion settings, and effects without the need to render a preview. To use this feature you need a video card that supports real-time capabilities. For information on real-time capabilities, see the documentation supplied with your real-time video card.

To set the area to be previewed (the work area):


Do any of the following:

- Drag the work area bar over the section you want to preview.



Grabbing the work area bar (left) and dragging it over the section to preview (right)

- Drag the work area markers to specify the beginning and ending of the work area.



Drag the work area markers to mark the beginning (left) and end (right) of the work area.

- Press Alt (Windows) or Option (Mac OS) as you click in the work area band above the series of clips you want to preview. This sets the work area to preview a continuous series of clips. The work area stops at the first gap detected between clips to the left and right of where you click.

- Double-click the work area band to preview only the section of the Timeline that is visible in the Timeline window.



To create a preview file for the work area but not play it back, choose Timeline > Render Work Area. This command saves time in final processing by creating a preview file while not requiring you to view the section after it has been rendered.

Previewing at final playback speed

You can preview the work area of your project at the final playback speed by building a preview on your system's hard disk (rendering). This method processes all effects and stores them in preview files on disk (see “Working with preview files” on page 232). The first time you preview, there may be a slight delay as effects are processed. However, once effects are processed, subsequent previews play back instantly unless you have edited effects within the work area since the last preview.

Premiere will not build an audio preview file to the hard disk unless the timeline audio tracks meet certain parameters concerning the number of audio tracks and the number of filters applied to those tracks. These parameters can be set manually. For information about setting these parameters, see “Audio settings” on page 78.

To enable previewing at final playback speed:

- 1 Choose Project > Project Settings > Keyframe and Rendering.
- 2 For Preview (under Rendering Options), select From Disk.
- 3 Click OK.

To preview the work area at the final playback speed:

Choose Project > Preview or press Enter (Windows) or Return (Mac OS).

Previewing by scrubbing the time ruler

To check edits or effects, you can drag the edit line in the Timeline window, an action known as *scrubbing*. The playback speed is dictated by the speed at which you drag.

To preview by scrubbing the time ruler:

Do one of the following:

- Drag the edit line in the time ruler. Premiere displays program frames without applied effects.
- To *render-scrub*, or scrub while previewing applied effects, press Alt (Windows) or Option (Mac OS) as you drag the edit line in the time ruler.
- To scrub while viewing only the alpha channel mask, press Shift+Alt (Windows) or Shift+Option (Mac OS) as you drag the edit line in the time ruler.

You can also use the Monitor source and program controllers to view frames without applied effects (see “Displaying a clip” on page 164).

Previewing to the screen

When you want to preview edits, transitions, and effects but you don’t care if the preview is at final playback speed, use the Preview to Screen option. With this option selected, Premiere renders as quickly as possible. Playback speed depends on image size and resolution, the number and complexity of effects and transitions, and the processing speed of your system. Previewing with this option may be significantly slower if you are viewing areas that include many effects. Unlike Preview from RAM, this option is not limited by the amount of available RAM.

To enable Preview to Screen:

- 1 Choose Project > Project Settings > Keyframe and Rendering.
- 2 For Preview (under Rendering Options), choose To Screen.
- 3 Click OK.

To preview using the Preview to Screen option:

Press Enter (Windows) or Return (Mac OS). To stop a preview, press Esc.

Previewing from RAM

Your previews will render quicker if you use the Preview from RAM feature. When you render a preview with this option selected, Premiere stores and processes the selected frames in RAM, instead of writing them to the disk and reading them back. This feature processes video, audio, and effects. If the video and audio information does not all fit in RAM, Premiere displays the message “Previewing from disk” and plays or renders a normal preview file on the disk. If there is enough RAM, the message “Retrieving Source Frames” is displayed and the preview is rendered in RAM.

If the processing demands are too great for your system, some frames are dropped during the preview. Remedy this situation by reducing the frame rate and frame size in the Video Settings panel of the Project Settings dialog box. Keeping the frame size small should also minimize the reduction in frame rate during previewing with this feature.

To view existing preview files when Preview from RAM is selected, use standard playback from the Timeline window or the source view of the Monitor window.

To enable Preview from RAM:

- 1 Choose Project > Project Settings > Keyframe and Rendering.
- 2 For Preview (under Rendering Options), choose From RAM.
- 3 Click OK.

To preview using the Preview from RAM option:

Press Enter (Windows) or Return (Mac OS). To stop a preview, press Esc.

Previewing an edit by synchronizing controllers

There may be times when you want the Source and Program views to move together. This is called *ganging* the monitors, and you use it to preview how a clip fits into the video program without having to actually add the clip to the program. For example, if you want to compare the action in a source clip to the time available for it in the program, you can start scrubbing the program at the proposed In point for the clip, and it will move in the Source view simultaneously with the Program view. You can then use the controllers to preview where the proposed Out points would fall in the source clip and existing program.

To synchronize the Source and Program view controllers:

- 1 In the Source and Program views, use each controller to go to the frame in each view from which you want to begin the synchronized playback.
- 2 In the Monitor window menu, choose Gang Source and Program to select it.
- 3 Use the jog tread, shuttle slider, Previous Frame button (◀), or Next Frame button (▶) on the controllers to compare frames (using other controls will turn ganging off). As you use one controller, the other controller moves the same amount of time in the same direction. There may be a slight delay as the controllers synchronize.

Previewing on another monitor

You can display the preview on any monitor connected to your computer. To accurately evaluate how your video program will look, you must connect a monitor that can display the program using the video standard of the target audience. For example, for a program intended for television viewing in North America, you would connect an NTSC monitor; for Europe, you would connect a PAL monitor. Previewing on another monitor requires video hardware that provides an appropriate video port for the preview monitor. Some video-editing cards and operating-system software products support a preview monitor independent of the desktop, and others support a preview monitor that is contiguous with the desktop so that it can also function as additional space for windows and palettes. See the documentation that came with your video-editing card and operating system software.

Working with preview files

When you preview a program, Premiere creates temporary files on your hard disk. These *preview files* contain the results of any effects that Premiere processed during a preview. If you preview the same work area more than once without making any changes, Premiere instantly plays back the preview files instead of processing the Timeline again. Similarly, preview files can save time when you export the final video program by using the processed effects already stored. Premiere stores the preview files in a folder you can specify.

To further save time, Premiere maintains existing preview files whenever possible. Preview files move along with their associated segment of the Timeline as you edit your project. When a segment of the Timeline is changed, Premiere automatically trims the corresponding preview file, saving the remaining unchanged segment.

The preview status for each clip in the Timeline window is indicated by a colored bar above the time ruler. When a preview file doesn't exist for a segment and needs to be generated, the indicator bar above that segment is red. When a preview file for the video segment exists, the indicator bar is green. When a preview for the audio segment exists, an additional bar attached below the indicator bar is light green. If all effects in a segment can be played in real time, there is no colored bar.

***Note:** To find the properties for audio preview files, choose Project > Project Settings > Audio. For information on audio project settings, see “Audio settings” on page 78.*

To specify the disk location for preview files:

- 1 Choose Edit > Preferences > Scratch Disks/Device Control.
- 2 For the Video Previews and Audio Previews menus in the Scratch Disks section, choose a location for video and audio preview temporary files, respectively. The disk you choose must be large and fast enough to support video playback, so choose a hard disk attached to your computer, not a network drive. Also, because Premiere must be able to locate the preview files when you open a project, avoid specifying removable media.
- 3 Click OK.

To delete preview files:

Do one of the following:

- To delete all preview files, move the cursor to the indicator bar while holding down Ctrl+Alt+Shift (Windows) or Command+Option+Shift (Mac OS). Click the indicator bar when the cursor becomes a trash can.
- To delete video preview files only, move the cursor to the indicator bar while holding down Ctrl+Alt (Windows) or Command+Option (Mac OS). Click the indicator bar when the cursor becomes a trash can labelled with the letter “V.”
- To delete audio preview files only, move the cursor to the indicator bar while holding down Ctrl+Shift (Windows) or Command+Shift (Mac OS). Click the indicator bar when the cursor becomes a trash can labelled with the letter “A.”

Playing back full-screen video

The Print to Video command plays a clip or the Timeline centered on a computer or television monitor. If the clip or Timeline is smaller than the full screen, it plays alone on a black background. This is useful for previewing the program in the Timeline, for viewing source clips or individual video files, or for television playback such as recording to videotape. Print to Video can double the size of the frame during playback so that you can play a quarter-screen video at full-screen size.

***Note:** Some video-capture cards do not support this feature, or support it differently. If you see different options than the ones documented in this section, see the documentation included with your video-capture card.*

To play a video on a black screen:

1 Do one of the following:

- To play the Source view in the Monitor window, activate the Source view.
- To play the program in the Timeline, activate the Program view in the Monitor window and make sure that the work area you want to preview is specified in the Timeline.
- To play a clip or sequence in its own window, activate a Clip window or Storyboard window (see “Adding multiple clips using an automated process” on page 201).

2 Choose File > Export Clip > Print to Video or File > Export Timeline > Print to Video.

3 Specify the following options as necessary, and then click OK:

- For Color Bars For, type the number of seconds to display color bars before playing the video.
- For Play Black For, type the number of seconds to display a black screen after the color bars (if specified) and before playing the video. For recording on videotape, displaying 15 seconds of black screen works well in many cases.
- Select Full Screen (Windows) or Zoom Screen (Mac OS) to scale the frame size to fill the screen for Print to Video only.

(Mac OS only) Choose Hardware from the Zoom Screen menu if you have a video card that supports hardware zooming; otherwise, choose Software.

If the frame size specified in Video Settings is less than about half the size of the display screen, the resulting picture may appear coarse or with obvious pixels; however, this effect may be less noticeable after recording on videotape.

- (Windows only) Select Zoom by 2 to double the height and width of the frame size for Print to Video only. This is useful for project frame sizes of 320 x 240 or smaller.
- For Screen Mode, choose Current to play on the main computer screen, or choose NTSC if you have an NTSC monitor connected to your system. The plug-in software included with some video-capture cards allows a temporary switch to the specified mode; see the documentation that came with your video-capture card.
- Select Loop Playback to replay the video continuously.

For information about recording the Timeline on videotape, see “Exporting to videotape” on page 338.

To stop Print to Video playback:

Press Esc.

http://



4



Chapter 4: Adding Transitions

The visual change from one clip to another is called a *transition*. To add nuance, texture, or special effects between video clips, Premiere provides a variety of transitions, such as wipes, zooms, and dissolves.

About transitions

The simplest transition is the *cut*, where the last frame of one clip leads directly into the first frame of the next. The term comes from film editing, where a cut means splicing two shots together. Very often, a cut is the most effective way to move from one scene to the next. Other transitions, however, are useful in setting a mood or adding a creative element to your project.

The transitions included with Premiere typically involve the end of one clip and the beginning of the next. For example, the Cross Dissolve transition might dissolve the last second of one clip into the first second of the next. Some transitions, such as Inset, can involve both clips in their entirety, depending on the desired effect. See “Changing transition settings” on page 248.

Using the Transitions palette

Premiere includes over 75 transitions, which you choose from the Transitions palette. Within the palette, transitions are organized by type, in folders. Each transition is represented by an icon depicting how it works, where A is the first clip and B is the second. To help you choose, you can animate these icons and view brief descriptions. In addition, you can preview the transition effect with actual frames from the two clips involved in the transition; see “Changing transition settings” on page 248. You can also customize the Transitions palette to group transitions together in folders or hide transitions that you don’t use often. The changes you make to a palette affect all projects.

To display the Transitions palette:

Choose Window > Show Transitions.

To view a description of a transition:

- 1 Display the Info palette, if necessary: choose Window > Show Info.
- 2 Select the transition in the Transitions palette. The description appears in the Info palette.

To customize the Transitions palette:

- To animate the icons, choose Animate from the Transitions palette menu.
- To stop icon animation, deselect Animate from the Transitions palette menu.
- To hide all transitions within a folder, click the triangle next to the folder name to collapse the folder.
- To hide selected transitions, select one or more transitions in the Transitions palette (Shift-click to select multiple transitions), and then choose Hide Selected from the Transitions palette menu.
- To restore hidden transitions, choose Show Hidden from the Transitions palette menu. The hidden transition appears dimmed. To restore the transition, select it and choose Show Selected from the Transitions palette menu.
- To reorder a transition in the palette, drag the transition up or down to a new location in its folder, or into another folder.
- To reorder a folder in the palette, drag the folder to a new location. With large folders, collapse the folder first.
- To create a new folder, click the New Folder button (□) or choose New Folder from the Transitions palette menu, type a name, and click OK. Drag transitions to the new folder.
- To rename a folder, select it, choose Rename Folder from the Transitions palette menu, type a name, and click OK.

- To delete a custom folder, select it, click the Delete Selection button (🗑️) or choose Delete Folder from the Transitions palette menu, and click Yes. The folder is removed, and all included files are placed in their original folders and dimmed.

Note: If you delete a default folder, the folder and all its contents are dimmed.


- To find a transition, click the Find button (🔍) or choose Find from the Transitions palette menu, type the name of the transition, and click Find. To find the next instance, click Find Again.
- To expand all the folders in the palette so you can view all the transition names, choose Expand All Folders from the Transitions palette menu.
- To collapse all the folders in the palette to preserve space or clean up the palette, choose Collapse All Folders in the Transitions palette menu.

Creating transitions

To add a transition, place it in the Timeline window between two clips. Transitions can be applied only to clips on the Video 1 tracks. You can also click the default transition button in the Monitor window (or use keyboard shortcuts in the Monitor or Timeline windows) to apply a default transition (see “Specifying and adding a default transition” on page 246). You can add a transition to the Video 1 track when the Timeline is in either Single-Track Editing mode or A/B Editing mode (see “Customizing track views” on page 173). However, switching between Single-Track Editing and A/B Editing after you have begun editing in the Timeline may cause unexpected or unpredictable behavior.

You can add the default transition between each clip automatically when you add clips to the Timeline using the Automate to Timeline command from the Project window menu or the Storyboard window menu. See “Adding multiple clips using an automated process” on page 201.

To enhance the transitions provided with Premiere, you can sequence two or more transitions together. To do this, use the A/B Editing mode and place the transitions side by side in the area where the clips overlap. For example, to create the effect of one clip pushing into and out of another clip, keeping the starting and ending clip the same, use two instances of the Push transition and reverse the direction setting for the second transition. See “Changing transition settings” on page 248.



Add two instances of one transition to the overlapping space (left) and reverse the direction setting for the second (right).


Working in the A/B Editing workspace

When you are working in the A/B Editing workspace or the Timeline is in A/B Editing mode, the Timeline uses three separate Video 1 tracks: Video 1A, Transition, and Video 1B. With this layout, you can visually determine the position and duration of a transition between two overlapping clips. For information on A/B Editing mode, see “Customizing track views” on page 173.

To add a transition to the Video 1 track in the A/B Editing workspace:

- 1 Position one clip in the Video 1A track and another clip in the Video 1B track so that some (or all) of the two clips overlap. The amount of overlap determines the default size of the transition.
- 2 If the Transitions palette is not visible, choose Window > Show Transitions.

- 3 Select and drag a transition from the Transitions palette to the Transition track in the Timeline window, between the overlapping area of the two clips. The duration of the transition is automatically adjusted to the overlapping area.



Transition placed (left) and automatically adjusted to fit overlapping area (right)

- 4 To lengthen or shorten the transition, make sure that the pointer tool is selected and press Control (Windows) or Command (Mac OS) as you drag the left or right edge of the transition. To reposition the transition between the clips, drag the transition itself.

Note: Once a transition is added, moving an edge of the transition can cause an edge of the affected clips to move correspondingly, and vice versa. To move a clip or transition edge independently, hold down Control (Windows) or Command (Mac OS) as you drag the edge.


- 5 Adjust transition settings, as described in “Changing transition settings” on page 248.
- 6 To preview the transition, see “Previewing transitions” on page 245.

Working in the Single-Track Editing workspace

You can add a transition between two clips when the Timeline is in Single-Track Editing mode. In general, this method requires more planning and is recommended for more experienced video editors, especially those with a traditional editing background.

To create a transition in Single-Track Editing mode, Premiere either uses the extra frames available for the clips (extra frames are created by trimming a clip), or repeats frames at the beginning or ending of the clips.

The single-track method of creating a transition is similar to the one in traditional linear editing studios, in which frames that you have trimmed out of the program (by setting new In or Out points, or using the trim, ripple edit, or rolling edit tools), are used to create a transition. The frames trimmed from the beginning of a clip are called head material; the frames trimmed from the end of a clip are called tail material. If insufficient head or tail material is present when applying a transition, Premiere displays a Fix Transition dialog box in which you can choose to change the duration of the transition, change the transition's alignment, or repeat the first and last frames of the clip and use those frames for the transition.



If you delete or move a transition (or a clip tied to a transition) after you've made adjustments using the Fix Transition dialog box, Premiere automatically restores the In and Out points of the corresponding clips.

To add a transition to the Video 1 track in Single-Track Editing mode:

1 If the two adjacent clips in the Timeline window do not already have extra frames that you can use for the transition, trim the Out point of the first by half the number of frames that will be used in the transition and the In point of the second by half the number of frames that will be used in the transition. (For example, for a 10-frame transition, trim the In and Out points by 5 frames each.) Then remove the resulting gap by selecting it and choosing Timeline > Ripple Delete.

2 Do one of the following:

- Drag a transition from the Transitions palette to the meeting point of the two clips. The overlapping area is highlighted as the pointer moves over the meeting point. The transition is applied, using the default transition duration. If insufficient frames are available, the Fix Transition dialog box appears.
- Hold down Alt (Windows) or Option (Mac OS) and drag a transition from the Transitions palette to the meeting point of the two clips. A dialog box opens in which you can set the effect (transition) duration and alignment.

3 To see the overlapping area on the Timeline, click the Uncollapse button (⌘) next to the Video 1 name.

4 To preview the transition, see “Previewing transitions” on page 245.

Previewing transitions

To preview a transition, you can either build a preview of, or render-scrub, the section of the Timeline containing the transition. With render-scrubbing, you can see the transition’s effect quickly, without waiting for Premiere to build a preview file.

To build a preview of the transition:

In the Timeline, move the yellow work area bar so it covers the transition and press Enter (Windows) or Return (Mac OS) to build a preview.

To render-scrub the transition:

Hold down Alt (Windows) or Option (Mac OS) and, when the cursor becomes a downward-pointing arrow (⬇), scrub in the Timeline window’s time ruler.

Adding QuickTime transitions

In addition to the transitions available in Premiere, you can add QuickTime transitions to a program. If you have installed QuickTime transitions, they will be available in the QuickTime folder in the Premiere Transitions palette.

To add a QuickTime transition:

- 1 In the Transitions palette, click the triangle to open the QuickTime folder.
- 2 Drag the QuickTime transition to the desired location in the Timeline.
- 3 In the Select Effect dialog box, choose the transition you want to add.
- 4 Modify the transition settings as needed, and then click OK.

Specifying and adding a default transition

The default transition can be applied quickly, without stopping to open the Transitions palette and drag the transition to the Timeline. Premiere automatically uses Cross Dissolve as the default transition, as it is one of the most commonly used transitions. If you frequently use another transition, you can set it as the default.

The technique you use to add a default transition depends on whether you are editing in Single-Track mode or A/B Editing mode.

To specify a default transition, and set the default duration and alignment:

- 1 If necessary, choose Window > Show Transitions.
- 2 Select the transition that you want to make the default.
- 3 From the Transitions palette menu, choose Set Selected as Default.
- 4 Type the default duration for the transition. (You can later change the duration, once the transition is added to the Timeline.)
- 5 Choose the default alignment for the transition. This setting applies to transitions added when using the Single-Track Editing mode; when you use A/B Editing mode, transitions always fill the overlapping space unless you physically resize them using the trim tool.
- 6 Click OK. These settings remain in effect for all projects until you change them.

To add the default transition to the Timeline:

- 1 Do one of the following:
 - When the Timeline is in A/B Editing mode, position one clip in the Video 1A track and another clip in the Video 1B track so that some (or all) of the two clips overlap.

- When the Timeline is in Single-Track mode, make sure that the Video 1 track is collapsed, and then position two clips on the Video 1 track so that they meet.

2 Position the edit line where the two clips meet or overlap.



You can easily move the edit line to the intersection between two clips by clicking the Next Edit (⏪) or Previous Edit (⏩) button in the Monitor window.

3 Do one of the following:

- In Single-Track mode, click the Apply Default Transition (⏪) button in the Monitor window, or press Ctrl+D (Windows) or Command+D (Mac OS). If extra frames are not available at the In and Out points of the adjacent clips, the Fix Transitions dialog box appears. If necessary, select options from this dialog box.

- In A/B Editing mode, expand the Video track in the Timeline if necessary, and then press Ctrl+Alt+Shift (Windows) or Command+Option+Shift (Mac OS) and click in the Transition track between two overlapping clips.

Replacing a transition


You can replace a transition by simply dropping a new transition on top of the old one. When you replace a transition, the alignment and duration are preserved; however, the settings for the old transition are discarded and replaced by the default settings for the new transition, or by the master transition settings if you have set them in the Transitions palette. See “Changing transition settings” on page 248.

To replace a transition:

Drag the new transition from the Transitions palette onto the existing transition in the Timeline window.

Changing transition settings

You can change a number of settings for each transition, including the transition direction, the start and end values, the border, and anti-aliasing. The following procedure describes how to display the Transition Settings dialog box and change settings common to many transitions. Settings specific to transitions are available by clicking Custom in the Transition Settings dialog box.



A. Start/End slider B. Border thickness C. Track selector D. Edge selector
E. Anti-aliasing selector F. Forward/Reverse selector

To change transition settings:

- 1 Open the Transition Settings dialog box in one of the following ways:
 - To change the settings for a single instance of the transition in the video program, in the Timeline either double-click the transition or select the transition and choose Timeline > Transition Settings.
 - To change the default settings of a transition for this and future projects, double-click the transition in the Transitions palette.
- 2 Adjust any of the following settings, and then click OK:
 - To see the starting and ending frames of the clips, select Show Actual Sources. This option is not available when you've double-clicked a transition in the Transitions palette.

- To change the initial and final appearance of the transition, use the Start and End sliders. (For example, if you want to create a picture-in-a-picture effect, use the Zoom transition and set the start and end sizes to about 30%; then add a border and move the center point to the desired corner.) Hold down the Shift key to move the start and end sliders together (for example, to set the start and end size of the transition to 30%).
- To adjust the width of the optional border on the transition, drag the Border slider. The default Border is None. Some transitions do not have borders.
- To select a border color, click the color swatch, select a color from the color selection window, and then click OK.
- To specify which clip begins the transition, click the Track selector on the left side of the transition's thumbnail to toggle back and forth starting with clip A (the left clip) or clip B (the right clip). You can also click this selector from the transition's thumbnail in the Timeline window if the thumbnail is large enough.
- To change the orientation of the transition, click an Edge selector on the transition's thumbnail. The Edge selectors are small triangles bordering the transition icon.

For example, the Barn Doors transition can be oriented vertically or horizontally. Some transitions do not have Edge selectors because the transition has only one orientation.

- To make the transition play forward or backward, click the Forward/Reverse selector in the upper right corner of the transition's thumbnail. For example, the Clock Wipe transition can play clockwise or counterclockwise.
- To adjust the smoothness of the transition's edges, click the Anti-aliasing selector in the lower right corner of the transition's thumbnail. Clicking cycles through the values Low, High, and Off.

Anti-aliasing smooths the edges or borders of the transition, improving its quality. You can also set anti-aliasing from the transition's thumbnail in the Timeline window.

- To adjust the center point of the transition, drag the small box that appears in the Start and End images. For example, the Iris Round transition can be centered toward the side or corner of the image.
- To change settings specific to the transition, click Custom. (Transitions without additional controls do not include a Custom button.)

Note: To change the duration of a transition in A/B Editing mode, hold down Ctrl (Windows) or Command (Mac OS) and drag an edge.

Using the Image Mask transition


You can use a black-and-white bitmap image as a transition mask in which image A replaces the black in the mask, and image B replaces the white in the mask. If you use a grayscale image for the mask, pixels containing 50% or more gray will be converted to black, and pixels containing less than 50% gray will be converted to white. Many third-party image collections can be used with this transition.

To add an image mask as a transition:

- 1 Drag the Image Mask transition from the Special Effect folder in the Transitions palette to the Transition track of the Timeline. The Image Mask Settings dialog box appears.
- 2 Click Select Image, and double-click the image file you want to use as a transition mask. The image you selected appears in the Image Mask Settings dialog box.



- 3 Click OK. To preview the transition, see “Previewing transitions” on page 245.



The Image Mask transition reveals the B clip through the white pixels of a selected image file, and the A clip through the black pixels.


Using the Gradient Wipe transition

Adobe Premiere can use any importable grayscale image as a gradient wipe. In a gradient wipe, image B fills the black area of the grayscale image and then shows through each level of gray as the transition progresses until the white area becomes transparent. When you create a Gradient Wipe transition, you can specify the “softness” of the transition’s edges. Many third-party image collections can be used with this transition.

To create a Gradient Wipe transition:


1 Drag the Gradient Wipe transition from the Special Effect folder in the Transitions palette to the Transition track of the Timeline. The Gradient Wipe Settings dialog box appears.

2 Click Select Image, and then double-click the file you want to use in the wipe. The image you select appears in the Gradient Wipe Setting dialog box.



3 Adjust the softness of the transition’s edges by dragging the Softness slider. As you drag the slider to the right, image A increasingly shows through image B.

4 Click OK. To preview the transition, see “Previewing transitions” on page 245.



Result of Gradient Wipe transition on clip

http://



5



Chapter 5: Mixing Audio

You can edit, add effects to, and mix up to 99 tracks of audio in Premiere. You can control volume and pan/balance settings of audio tracks directly within the Timeline, or use the Audio Mixer window to make changes in real time. Premiere also provides a wide range of built-in controls for *audio sweetening*, or sound processing. For example, you can apply equalization and delay effects to an audio clip. As with video effect plug-ins, you can add more sound capabilities by using audio plug-ins. A number of audio plug-ins are included with Premiere; others are available separately.

Basic editing procedures for audio-only clips are virtually identical to those for editing a video clip, such as setting In and Out points, speed, and duration. When you edit a video clip linked to an audio clip, your edits are applied to both video and audio. See “Chapter 3: Editing Video.”

You control how audio plays back from the Timeline by specifying settings in the Project Settings dialog box, and you control how audio is processed during export by specifying settings in the Export Movie dialog box. See “Audio settings” on page 78 and “About exporting video from Premiere” on page 337, respectively.

Understanding how Premiere processes audio

You can process an audio clip in several ways: adjusting volume and pan/balance levels (either directly in the Timeline or by using the Audio Mixer window), choosing a menu command for a selected clip, or applying an audio effect. Understanding the order in which Premiere processes audio can help you plan audio adjustments.

When you preview, play, or export a video, Premiere first converts its audio (one frame at a time) using the settings you specify in the Audio Settings dialog box. If you selected stereo as one of the audio settings, additional stereo commands located in the Clip > Audio Options menu (such as Duplicate Left or Mute Right), are then processed. Audio effects you have applied are processed next, followed by any pan/balance or volume adjustments in the Timeline audio track for the clip. Finally, Premiere processes any gain adjustments you applied using the Clip > Audio Options > Audio Gain command.

Adjusting gain

You can set the overall *gain* of a clip. Although your gain setting is processed after volume, pan/balance, and effects are processed, it will not remove any of these settings. Setting the gain is useful to balance the gain levels of several clips or to adjust a clip's audio signal when it is too high or too low. Keep in mind, however, that if the gain in an audio clip was set too low when it was digitized, increasing the gain may emphasize noise or introduce distortion. For best results, follow the standard practice of making sure that the gain level is correct at the time the audio clip is digitized.

Adjust audio levels and create cross-fades by adjusting the volume for isolated sections of a clip, either directly on the Timeline or in the Audio Mixer window. For information on adjusting volume on isolated sections of a clip, see “Adjusting audio levels in the Timeline” on page 257. For information on adjusting audio levels in the Audio Mixer window, see “Adjusting audio levels in the Audio Mixer window using automation” on page 266.



For more control over gain, use the Compressor/Expander effect; see the topic “Compressor/Expander” in online Help.

To adjust gain uniformly throughout a clip:


- 1 In the Timeline, select an audio clip with the selection tool or select multiple audio clips using the range select tool.
- 2 Choose Clip > Audio Options > Audio Gain.
- 3 Do one of the following:
 - Type a Gain value. A value above 100% amplifies the clip. A value below 100% *attenuates* the clip, making it quieter.
 - Click Smart Gain to have Premiere set an automatic maximum gain value, up to 200%. This value represents the percentage of amplification necessary to boost the loudest part of the clip to full strength (the loudest sound your system can reproduce).
- 4 Click OK.

Adjusting audio levels in the Timeline

The red *volume rubberband* allows precise adjustment of the volume level at any point during the clip. Specify the adjustment point by creating a *handle* on the rubberband. A handle marks the beginning and ending of a *rubberband segment*, and you can drag the handle up or down to change the audio level. All audio clips include two handles that you can't remove—one at the beginning of the clip, and another at the end. You can also *cross-fade* two audio clips automatically so that one fades out as another fades in. The rubberband in the Timeline corresponds to the volume fader in the Audio Mixer window, and serves the same purpose. The way you create fades in these two windows differs, however. In the Timeline, you visually adjust levels. In the Audio Mixer window, you adjust levels in real time as you listen to the track. Also, for each track in the Timeline, there is one volume rubberband per *clip*, while in the Audio Mixer window, there is one volume fader per *track*. For more information, see “Adjusting audio levels in the Audio Mixer window using automation” on page 266.

To adjust volume at a specific point:


- 1 If necessary, click the triangle to the left of the track name to expand the audio track you want to adjust.



Clicking the triangle to expand the track (left), and the track after it expands (right)

- 2 If the red volume rubberband is not displayed in the clip, click the red Volume Rubberband icon (■) in the track header.

- 3 With the selection tool selected, position the pointer over a part of the red volume rubberband where you want to create a new handle. The pointer changes to a pointing finger with red plus and minus signs.
- 4 Click to create a new rubberband segment.
- 5 Drag the volume handle up or down to adjust the slope of adjacent rubberband segments. An upward slope indicates an increase in volume; a downward slope indicates a decrease in volume.



Creating a new volume handle (left), and the result of dragging it up to increase volume (right)

 If you activate the Info palette before you drag, you can watch the volume level update in the Info palette as you drag.

To remove a volume handle:

Drag a volume handle above or below the audio track and release the mouse.

To adjust volume in 1% increments:

- 1 If necessary, click the triangle to the left of the track name to expand the audio track you want to adjust, and then click the red Volume Rubberband icon (■).
- 2 Click the volume rubberband to create a new volume handle if necessary.
- 3 Position the pointer over the volume handle you want to adjust so that the pointer changes into a pointing finger with red arrows. Press and hold Shift as you drag the volume handle up or down. A numeric display appears over the audio track to indicate the current volume level as you drag. As long as you hold the Shift key, you can drag beyond the top and bottom of the audio track, if necessary. The larger drag area lets you adjust volume in 1% increments, as indicated in the numeric display.

To adjust two handles simultaneously:

- 1 If necessary, click the triangle to the left of the track name to expand the audio track you want to adjust, and then click the red Volume Rubberband icon (■).
- 2 Select the fade adjustment tool (⌘).




- 3 Position the fade adjustment tool between the two handles you want to adjust, and then drag that segment up or down.

In some situations you may want to leave the volume level of the previous rubberband segment intact and fade sharply from there. This requires two handles: one to hold the previous gain level, and another to set the starting level for the following segment. Use the fade scissors tool (⌘) to automatically create two new adjacent handles on the fade control.

To create two adjacent fade handles:

- 1 If necessary, click the triangle to the left of the track name to expand the audio track you want to adjust, and then click the red Volume Rubberband icon (■).
- 2 Select the fade scissors tool (⌘).



- 3 Click the Volume rubberband where no handles exist. This creates two adjacent handles, although they may be too close together to see separately.
- 4 Select the selection tool, and drag the new handles as needed.

 *If you want more room to drag the volume handle within an audio track, choose Timeline Window Options from the Timeline window menu, select a larger Icon Size, and click OK. However, pressing the Shift key as you drag the volume handle still provides the most precision.*

To cross-fade between two audio clips:

- 1 If necessary, click the triangle to the left of each track name to expand the audio tracks that you want to cross-fade.
- 2 Make sure that the two audio clips overlap in time. Two clips cannot overlap on the same track, so you must place each audio clip on a different audio track.
- 3 Select the cross-fade tool (⌘⇧⌘).




- 4 Click the clip you want to fade out.
- 5 Click the clip you want to fade in. Premiere automatically creates and adjusts volume handles on both clips.

Note: When creating a cross-fade, the order in which you select the clips is not important.

Cross-fading clips linked to video

When audio clips are linked to video clips that don't overlap, cross-fading the audio clips is more complex than an audio-only cross-fade. The audio clips linked to video clips cannot be dragged to overlap if the video clips are on the same track. You can solve this problem by moving the clips onto different tracks. First turn off Sync mode, so that you can move or trim a clip independently of its linked video or audio.

Cross-fading audio linked to video is useful when performing a *split edit*, in which a clip's video and audio start or end at different times. In one version of a split edit, called an *L-cut*, the audio Out point is later than the video Out point so that you can continue playing a video clip's audio after the next video clip's In point. Another kind of split edit is an *audio lead*, called a *J-cut*, which you use when you want an audio/video clip's audio to start playing before the video In point.



In an *L-cut*, the audio Out point is later than the video Out point (left); in a *J-cut*, the audio In point is earlier than the video In point (right).

Note: Cross-fading existing clips in the Timeline usually requires extending the duration of one or more audio clips. Whenever you extend the duration of a clip, additional frames must be available in the clip's source (master) clip beyond the current In or Out point. For example, if you didn't trim the beginning or ending of a source clip before adding it to the Timeline, the clip is already using all frames available from its source, so its duration cannot be extended.

To cross-fade audio clips linked to nonoverlapping video:

- 1 If necessary, click the triangle to the left of each track name to expand the audio tracks you want to adjust.
- 2 Click the Toggle Sync Mode button (⌘) to deselect Sync mode. See “Linking video and audio clips in the Timeline” on page 217.
- 3 Drag one audio clip to a track where the audio can overlap the other audio clip in time. The tracks do not have to be adjacent.

- 4 Drag the In or Out point of one audio clip to extend it as far past the edge of the other audio clip as needed. Make sure that only the In or Out point is moving, not the entire audio clip.
- 5 Select the cross-fade tool (⌘⇧).
- 6 Click the clip you want to fade out, and then click the clip you want to fade in. Premiere automatically creates and adjusts fade handles on both clips.
- 7 Click the Toggle Sync Mode button again to select Sync mode.

Panning or balancing a clip

You can *pan* a monophonic audio clip to set its position between the left and right stereo channels. For example, if an audio clip contains one person's dialogue, you can pan the audio to match the person's position in the frame.

You cannot pan a stereo audio clip because both channels already contain audio information. When you work with a stereo audio clip, the pan control adjusts the balance of the stereo channels within the clip.

As with volume adjustments, you can pan or balance a clip in either the Timeline or the Audio Mixer window. The Pan rubberbands in the Timeline correspond to the pan/balance controls in the Audio Mixer window and serve the same purpose. For information on panning and balancing a clip in the Audio Mixer window, see “Panning or balancing in the Audio Mixer window using automation” on page 269.

Panning or balancing clips in the Timeline

You can vary the pan or balance freely along the duration of the clip by adding and dragging handles on the blue *Pan/balance rubberband* on the audio clip, using techniques similar to those you use for adjusting volume.

For best results when previewing panning or balancing, make sure that your computer or audio card is connected properly to speakers in stereo. Make sure that the left and right channels are not reversed.

To pan or balance an audio clip:

- 1 If necessary, click the triangle to the left of the track name to expand the audio track you want to adjust.
- 2 If the blue Pan/balance rubberband is not displayed in the clip, click the blue Pan/balance icon () in the track header.
- 3 Position the pointer over the spot on the pan/balance handle you want to adjust, so that the pointer changes into a pointing finger with blue arrows. Drag the pan/balance handle up to pan or balance left, or down to pan or balance right.

To pan or balance a clip in 1% increments:

- 1 Position the pointer over the pan/balance handle you want to adjust, so that the pointer changes into a pointing finger with blue arrows.
- 2 Press and hold Shift as you drag the pan/balance handle. A numeric display appears over the audio track to indicate the current pan or balance level as you drag. As long as you hold the Shift key, you can drag beyond the top and bottom of the audio track. The larger drag area lets you pan or balance in 1% increments to the left or right with the center at 0%, as indicated by the numeric display.



Premiere can cyclically pan a monophonic audio clip over the duration of a clip by using the Auto Pan audio effect. See the topic “Auto Pan” in online Help.

Working with the Audio Mixer window

In the Audio Mixer window, you can adjust the volume level and pan/balance of multiple audio tracks while listening to them and viewing the video tracks. Premiere uses automation to record these adjustments and then to apply them as the clip plays back. The Audio Mixer window, like an audio mixing console, contains a set of controls for each audio track, which is numbered according to the corresponding audio track in the Timeline. Using the mouse, drag a track's volume fader to adjust its volume over time. As you make adjustments using the Audio Mixer window, Premiere creates handles in the audio clip's volume rubberband in the Timeline and applies your changes. The level setting for a track in decibels (dB) is displayed directly below its volume fader, and you set a level by typing a value from +6 to -95 in this box and pressing Enter (Windows) or Return (Mac OS). Audio level is represented graphically by a segmented VU meter to the left of the volume fader. The small indicator at the top of the VU meter turns red when the level is high enough to cause *clipping*, or distortion.

Each track of the mixer also contains a pan/balance control, so that you can pan a monophonic clip from left to right or balance a stereo clip. Change the setting of this control either by dragging clockwise or counterclockwise, or by typing a value from -100 to +100 in the box below the control and pressing Enter (Windows) or Return (Mac OS).

You can start and stop recording automation changes at any point in the audio track using the transport controls at the bottom of the Audio Mixer window

For each audio track, three buttons determine the automation state during the mixing process:

Automation Write () Reads the stored level and pan/balance data for an audio track and records any adjustments you make to these settings using the volume and pan/balance controls in the Audio Mixer window. These adjustments are stored as new handles on the Volume and Pan/balance rubberbands in each clip in the Timeline track. In Automation Write mode, the function of the track controls is determined by the Automation Write Options selections in the Audio Mixer Window Options dialog box. For information on this dialog box, see “Adjusting audio levels in the Audio Mixer window using automation” on page 266.


Automation Read () Reads the stored volume and pan/balance data and uses it to control the audio level of the track during playback.

Automation Off () Ignores the stored volume and pan/balance data during playback. Automation Off is the default mode for Premiere, allowing real-time use of the mixer controls without interference from the rubberbands in the Timeline.

Each audio track in the mixer also includes buttons to specify which tracks are monitored during playback of your program in the Audio Mixer window. Select Mute to silence a track, and select Solo to monitor a track and mute all others that do not have Solo selected. If neither button is selected on any track, then all the tracks will be audible.

Gang tracks to apply relative dB levels to multiple tracks simultaneously. For example, if you want to make a change of -2 dB to audio volume levels in tracks 1, 3, and 4 simultaneously, gang those three volume fader controls and then drag any one of them -2dB. Assign volume fader controls to one of four gang numbers using the volume fader context menu within the Audio Mixer Window. When a volume fader control is assigned to a gang, its handle changes color to indicate its gang assignment.

The Audio Mixer window also includes controls for playing back your program while mixing it. For descriptions of these controls, see “Using Monitor window controllers” on page 166.



*A. Track name B. automation buttons C. Mute/Solo buttons
D. Pan/Balance control E. Pan/Balance indicator/entry field
F. clipping indicator G. volume fader control H. VU meter
I. dB level indicator/entry field J. transport controls*

You can modify the Audio Mixer window so that you see only the audio tracks or only the master fader, or both. By default, the Audio Mixer window displays both the audio tracks and the master fader.

To modify the Audio Mixer window:

1 Right-click (Windows) or Control-click (Mac OS) the title bar of the Audio Mixer window to open the Audio Mixer Window Options dialog box, and do one of the following:

- To display the audio tracks without the master fader, choose Audio Tracks Only.
- To display the master fader without the audio tracks, choose Master Fader Only.
- To display both the audio tracks and the master fader together, choose Audio Tracks and Master Fader.

Adjusting audio levels in the Audio Mixer window using automation

Using automation in the Audio Mixer window, you can set audio track levels and pan/balance tracks in real time as you listen to the audio track. Once the adjustments have been applied, fine-tune your changes directly in the Timeline by dragging the handles on the Volume rubberbands in each clip.

***Note:** Audio Mixer window tracks are not functional when playing back segments of Timeline audio tracks containing previews. The Master Fader, however, remains functional. Use the Audio Mixer before applying audio effects that may cause preview files to be created.*

To use automation to adjust the volume for part or all of a track:

- 1 If necessary, click the triangle to the left of the track name to expand the audio track that you want to adjust.
- 2 Drag the edit line to the point where you want to start recording automation changes.
- 3 Choose Window > Audio Mixer.
- 4 In the Audio Mixer window, locate the mixer track that corresponds to the Timeline track you want to adjust (for example, Track 1 controls the Audio 1 track). The track name appears at the top of each mixer track.
- 5 Click the Automation Write button () at the top of the mixer channel. To make changes in additional tracks, click the Automation Write button for those tracks also.
- 6 Right-click (Windows) or Control-click (Mac OS) the title bar of the Audio Mixer window to open the Audio Mixer Window Options dialog box. In the Automation Write Options section, choose one of the following and click OK:
 - Choose Touch to modify the stored volume level and pan/balance data only while you drag the volume fader and pan/balance controls. When you release the mouse button, the controls return to their original position.
 - Choose Latch to modify the stored volume level and pan/balance data while you drag the volume fader and pan/balance controls, and to subsequently retain those control settings. When you release the mouse button, the controls remain in their adjusted position.

- Choose Write to modify the stored volume level and pan/balance data based on the current position of the audio track controls. You will not need to drag the controls during recording to begin the write process. This choice is useful if you want to preset and then maintain a particular control setting throughout a recording or to write automation immediately at the start of playback.
- Choose Write/Touch to use Write mode for the next playback, but then to have Premiere automatically switch to Touch mode for subsequent playbacks.

***Note:** You can gang tracks in order to make volume changes to several tracks at once, but because you have only one mouse and pointer, you cannot operate each volume fader independently. To make different changes to multiple tracks, play the program a number of times, recording changes for one track at a time. For information on ganging tracks, see “To adjust volume for more than one track at a time” later in this section.*

- Choose one option from the Enable Automation Of drop-down menu. Choose Volume and Pan to modify both the volume and pan/balance data in the clip; choose Volume Only to modify only the volume level; choose Pan Only to modify only the pan/balance data.

7 Click the Play button (▶) in the Audio Mixer window to start recording. You can also click the Loop button (♻) to play the program in a continuous loop or click the Play In to Out button (▶) to play from the In Point to the Out point.

8 Drag the volume fader up to increase volume level or down to decrease volume level. To avoid distortion, adjust the volume so that the VU meter to the left of the volume fader displays only yellow on the peaks, not red. The clip indicator remains red once the volume reaches clipping levels. To reset the clip indicator once it turns red, lower the volume fader and click the clip indicator.

9 To stop recording, click the Stop button (■). To prevent accidentally overwriting automation that has already been applied, click the Auto Read button (🔍) for the track you just recorded.

10 To preview your volume changes, drag the edit line to the beginning of your changes and click the Play button (▶).

To adjust volume for more than one track at a time:

1 Gang the audio tracks you want to work on: Right-click (Windows) or Control-click (Mac OS) the volume fader you want to assign to a gang and choose a gang number from the context menu. Repeat this process for the other channels you want to gang, assigning each the same gang number.

- 2 Click the Automation Write button () for each audio track in which you want to make changes.
- 3 Set your Automation option to either Write or Write/Touch and record your track volume changes, as described in the previous procedure. As you adjust a volume fader on any one of the ganged tracks, the change is applied to all ganged tracks.

To ungang the audio tracks:

Do one of the following:

- To remove a volume fader from a gang, right-click (Windows) or Control-click (Mac OS) each ganged volume fader and choose No Gang.
- To temporarily override the ganging, hold the Shift key while dragging the volume fader.

To select tracks to be monitored during playback:

Do one of the following:

- To monitor one or more tracks, click the Solo button for the corresponding tracks.
- To mute one or more tracks, click the Mute button for the corresponding tracks.

Understanding nonlinear volume changes

A rubberband segment between any two adjacent handles in the Timeline is linear; each handle is connected to the next handle by a straight line. Volume adjustments you make using the Audio Mixer window can be linear or nonlinear, depending on the rate at which you drag a volume fader. Although linear volume changes provide a quick and simple way to change volume, they do not always sound natural to the human ear. Sounds derived from physical objects, such as a bell, fade away at a nonlinear rate. You can approximate a nonlinear volume change in the Timeline by positioning volume rubberband handles along a curve.

Selecting the Logarithmic Audio Fades option in the Audio Settings portion of the Project Settings dialog box (see “Audio settings” on page 78) converts linear volume changes to logarithmic volume changes when you play or preview the project. Likewise, selecting the Logarithmic Audio Fades option in the Audio Settings portion of the Export Movie Settings dialog box (see “Exporting a video” on page 346) converts linear volume changes into logarithmic volume changes in an exported movie. When you select this option, the linear volume changes you create in the Timeline are still linear in the project; only the output changes.

Panning or balancing in the Audio Mixer window using automation

You can pan a monophonic clip or balance a stereo clip by using the Pan/Balance control in the Audio Mixer window.

To pan or balance an audio clip in the Audio Mixer:

- 1 If necessary, click the triangle to the left of the track name to expand the audio track you want to adjust.
- 2 Drag the edit line to the point where you want to start recording automation changes.
- 3 If the Audio Mixer window is hidden or is not displayed, choose Window > Audio Mixer.
- 4 Click the Auto Write button () in the mixer channel that you want to pan or balance.
- 5 Select an option from the Automation Write Options section. For information on these options, see “Adjusting audio levels in the Audio Mixer window using automation” on page 266
- 6 Click the Play button () in the Audio Mixer window to start recording.
- 7 Click the pan control and drag outside it, and then drag clockwise to pan or balance right, or counterclockwise to pan or balance left. Dragging outside the pan control gives you greater precision in adjusting it.



- 8 To stop recording, click the Stop button ().
- 9 To preview your changes, choose the Auto Read () button to prevent accidentally overwriting applied automation, drag the edit line to the beginning of your changes, and click the Play button.

Using a clip's left or right stereo channel only

Use the Duplicate Left and Duplicate Right commands to replace an entire audio clip with its left or right channel only. For example, you can create a full, balanced audio clip from a clip originally recorded only in the left or right stereo channel.

To use one stereo channel for an entire audio clip:

- 1 Select an audio clip in the Timeline.
- 2 Do one of the following:
 - Choose Clip > Audio Options > Duplicate Left to use the left channel.
 - Choose Clip > Audio Options > Duplicate Right to use the right channel.
 - Choose Clip > Audio Options > Normal to restore the clip's original stereo channels.

Muting one channel of a stereo clip

Muting one channel of a stereo audio clip in the Timeline window can be useful if one channel contains unwanted noise or if the channels were recorded out of phase.

To mute one stereo channel in an audio clip:

- 1 Select an audio clip in the Timeline.
- 2 Do one of the following:
 - Choose Clip > Audio Options > Mute Left to mute the left channel.
 - Choose Clip > Audio Options > Mute Right to mute the right channel.
 - Choose Clip > Audio Options > Normal to restore the clip's stereo channels.

Swapping channels in a stereo clip

You can swap the channels in a stereo audio clip in the Timeline window. You would typically do this if the channels were incorrectly recorded left-to-right.

To swap the stereo channels in an audio clip:

- 1 Select an audio clip in the Timeline.
- 2 Do one of the following:
 - Choose Clip > Audio Options > Swap Channels to reverse the channels.
 - Choose Clip > Audio Options > Normal to restore the orientation of the clip's stereo channels.

Viewing audio clips

You can view an audio clip's Volume or Pan rubberbands and its waveform in the Timeline. You can also view an audio clip in its own window, which is useful in situations such as setting precise In and Out points (see “Setting an audio source In point between timebase divisions” on page 183).

To view audio clips:

Do one of the following:

- To view the audio waveform of a clip in the Timeline, click the triangle to the left of the audio track name, and then click the Waveform icon (). Make sure that you have set the Draw Audio When View *n* or Closer option in the Timeline Window Options dialog box to a figure that allows for the display of a waveform (for more information on the Draw Audio When View *n* or Closer option, see “Customizing the Timeline window” on page 172).
- To view an audio clip in its own window when it is currently in the Timeline, press Alt (Windows) or Option (Mac OS) as you double-click the clip.
- To always view an audio clip in its own window, choose Preferences > General, select Open Movies in Clip Window, and click OK.
- To override the current window preference for viewing clips (described in the previous paragraph), press Alt (Windows) or Option (Mac OS) as you double-click a clip in the Project window. For example, if you set your preferences to open clips in their own windows, pressing Alt/Option opens a clip in the Source view.

http://



6



Chapter 6: Creating Titles

Use Premiere's Title window to create type and graphics. A title can include straight lines, shapes, and rolling credits. Once you create a title, you use it in your project just like any other source clip, by editing it into your video program using cuts and transitions, or by superimposing it over other clips.

Creating and setting up a new title

Even though you can create a title while working in a project, a title is an independent file, separate from your project. Like any other clip, it doesn't become part of your video program until you add it to the Timeline. You can work with more than one open Title window at a time, or use a title in more than one project.

***Note:** You can also create a title in another graphics application, save it in a graphics format compatible with Premiere, and import it into Premiere; or use a third-party Title application and import the resulting title file into Premiere.*

To start and save a new title:

- 1 Choose File > New > Title.
- 2 Choose File > Save As.
- 3 Specify a location and filename, and then click Save.

Importing a sample frame

When you import a sample frame from a clip (or still image), the frame functions only as a positioning aid for title type and graphics and is not actually included in the title clip. You can select and use any color from the sample frame by using the eyedropper tool () . By default, Premiere uses the first frame in the clip (or the poster frame if one is defined), but you can specify which frame to use by setting marker 0 (Poster Frame) in the clip. See "Using markers" on page 185.

To import a sample frame to the Title window for positioning:

- 1 Open the Title window.


2 Do one of the following:

- If a project is already open, double-click any clip in the Project window.
- If no project is open, choose File > Open, locate the video clip or still image file you want to use as a reference, and click OK.

3 In the Clip or Source view window, go to the frame you want to use for title positioning.

4 Click the Marker Menu button (⏏) and choose Mark > 0 (Poster Frame). This specifies the frame Premiere uses for the Title window.

5 Drag the frame into the Title window.



Dragging a frame from the Source view window (right) to the Title window (left).

To change a sample frame:

1 Open the clip in the Clip or Source view window and locate the frame you want to use as the sample frame.

2 Click the Marker Menu button (⏏) and choose Mark > 0 (Poster Frame). The frame at the new marker 0 position will automatically appear in the Title window.


To remove a sample frame:

Select Title > Remove Background Clip.

Setting Title window options

Use the Title window options to specify the size of the title area, a background color, and safe zones. Safe zones are useful when editing for NTSC broadcast and videotape, because most NTSC consumer television sets cut off some portion of the outer edges of the picture. This process, called overscan, permits the center of the picture to be enlarged. The amount of overscan is not consistent across all televisions, so it is best to keep titles within the *title-safe* zone and important subjects within the *action-safe* zone. The Title window options include an option to display NTSC title-safe and action-safe zones. For best results, play back the video on a television monitor connected to your computer (see “Previewing on another monitor” on page 232).

Note: *The safe zones indicated by Premiere represent only NTSC video and are only guidelines for other video standards such as PAL or SECAM.*



Title-safe (A) and action-safe (B) zones

To set Title window options:

- 1 With the Title window open, choose Window > Window Options > Title Window Options, or right-click (Windows) or Control-click (Mac OS) in the Title window and choose Title Window Options from the context menu.
- 2 Specify the following settings as necessary, and then click OK:
 - For Size, type the dimensions in pixels that you want to use for your title frame, such as 320 horizontal (h) and 240 vertical (v).
 - For Aspect, select the pixel aspect ratio you will use to output your final video.

- For Background, click the box to specify a background color (see “Using the color picker” on page 290). If you want the background color to be visible in Premiere, select Opaque.
- Select Show Safe Titles to display NTSC title-safe and action-safe zones.
- Select NTSC-Safe Colors to automatically move colors that are outside the NTSC-safe range into the NTSC-safe range when the title is rendered. This option may mute colors somewhat. If you are creating titles for NTSC television and you do not select this option, colors outside the NTSC-safe range may display poorly or bleed across television scan lines.



When the Title window is active, set the background color to black or white from the keyboard by pressing B for black or W for white.

To speed up display using the Draft option:

Select Draft in the Title window. The Title window displays faster, at the expense of quality. The Draft option affects the display in the Title window only; the title displays at full quality when you use it in a video program.

To select text and graphic tools:

Do one of the following:

- To select a tool for one operation, click the tool in the toolbox (except the selection tool). The toolbox highlights the tool in gray, and the tool reverts to the selection tool after one use.
- To select a tool for continual operation, double-click the tool in the toolbox (except the type tool, which always reverts to the selection tool after one use). The toolbox highlights the tool in black, and the tool remains active until you select another tool.



Get quick access to most formatting options by right-clicking (Windows) or Control-clicking (Mac OS) an object and choosing a command from the menu.

Creating text objects

Use the tools and commands in the Title window to create objects containing text that are known as text *objects*. You can choose a number of text formatting options and a wide range of fonts, including PostScript or TrueType fonts. When you change text attributes, the change affects all future items.

Compared to paper, video displays at a much lower resolution and is viewed from much farther away (often from across a room). For maximum legibility, use the following guidelines when specifying type for video:

- Use large sans-serif fonts. Avoid small type and serif fonts; the thin strokes of some small or serif characters do not display well on interlaced television sets, causing them to flicker.
- Use semibold and boldface type weights, which are generally easier to read on television than regular or light type weights.
- Use few words in your titles. Long paragraphs of small type are difficult to read on television.
- When designing a title to be superimposed, use colors that contrast well with the background video. You can import a sample frame to check a title against its background (see “Importing a sample frame” on page 275). If the background is complex, consider adding a shadow (see “Adding a shadow” on page 286) or a semitransparent shape behind the type (see “Creating graphic objects” on page 284).
- Make sure that the fonts you use in the title file are installed on any other computer where you plan to open the title file or the project that includes it. Font names are often different between Windows and Mac OS, even when the fonts are identical. After you complete editing and record the final cut on videotape or export it to a video file, you no longer need the title fonts.

To create text:


- 1** Select the type tool (T).
- 2** Click to position the top left corner of the text object in the Title window, and type the text you want.
- 3** When the type is complete, click outside the text.

The new text uses the current color, transparency, and gradient settings. See “Using color, transparency, and gradients” on page 287.


To edit existing type:

1 Choose how your edits will affect the text by doing one of the following:

- To change attributes uniformly within a text object, select the selection tool (☛) and click the text. The entire text object is selected, and handles appear at the corners of the text object.



- To edit the text or apply different type attributes to individual characters, select the type tool, click a text object, and then drag to select the text you want to change. For example, you can apply a different color and size to one of the words in a title.



Note: The selection tool overrides uniquely formatted characters. For example, if you use the type tool to apply a blue color to one word, and then you use the selection tool to apply a red color to the text object containing the blue word, all the characters in the text object become red. However, any text attributes you don't change remain intact.

2 Do any combination of the following:

- To change the font, choose Title > Font and select a font. In Windows, click OK.

- To change the type style, choose Title > Style and select a style. (In Windows, you can also change the style by choosing Title > Font and selecting a new style from the Style menu.) The Plain, Bold, Italic, and Underline styles work as they do in a word processor. The Emboss style creates a slightly offset copy of the text behind the original text.
- To change the font size, choose Title > Size and choose a type size. (In Windows, you can also change the size by choosing Title > Font and selecting a new size from the Size menu.)
- To change the color, see “Using color, transparency, and gradients” on page 287.
- To specify spacing between lines, choose Title > Leading and choose a leading (line spacing) adjustment from the menu. Reset Leading restores the default leading for the font.
- To kern (adjust the spacing between characters), click an insertion point between the letters you want to kern, or select a range of characters. Then click the Decrease Kerning button (◀) to remove space between characters or click the Increase Kerning button (▶) to add space between characters.
- To change paragraph alignment, click an insertion point in the paragraph you want to align, choose Title > Justify, and choose an alignment.



Edit existing text by double-clicking text with the selection tool. Premiere changes the selection tool to the text tool so that you can select individual characters.

To stretch type:

With the selection tool, click a text object. Hold down Ctrl (Windows) or Option (Mac OS) as you drag any of the object handles. The selection tool changes to a stretch tool as you drag.

Changing text orientation

By default, a line of text displays from left to right. You can specify vertical orientation so that a line of text displays from top to bottom. This is useful for creating titles in languages such as Japanese, or as a text effect.

Note: *To rotate text freely, apply motion settings to the title after you add the title to the Timeline (see “Rotating, zooming, delaying, and distorting” on page 316), or prepare the title in another application such as Adobe After Effects.*

To change the orientation of text:

With the selection tool (⌘), click a text object. Choose Title > Orientation and select Horizontal or Vertical.


Creating rolling and crawling text

You can make text *roll* (move vertically up or down across the screen) or *crawl* (move horizontally left or right).

When you add the title to a program, the speed of moving text is determined by the duration you specify for the title in the Timeline. For example, if you originally specified a duration of 20 seconds for a rolling title, and then you change the duration to ten seconds, the title must roll twice as fast to move the same number of lines across the screen in half the time.

To create rolling or crawling type:

- 1 Select the rolling title tool (⌘).
- 2 Drag to specify the size of the text object that will contain the rolling title.



Dragging the rolling title tool (left) creates an empty rolling title text object (right).

- 3 Type the text you want in the title.

Note: To make the text roll or crawl, you must type enough text to overfill the text box. If you don't have enough text, overfill the box using blank spaces. To create blank spaces for rolling text, press Enter (Windows) or Return (Mac OS). To create blank spaces for crawling text, press the spacebar.

- 4 With the rolling title still selected, choose Title > Rolling Title Options.
- 5 In the Direction section, select the direction in which you want the type to move.
- 6 Select Enable Special Timings if you want more control over rolling or crawling motion. Then specify the following values as needed and click OK:
 - For Pre Roll, specify how many frames you want to appear motionless (starting with the title clip In point to the frame in which the title starts moving).
 - For Ramp Up, specify how many frames the clip should use to accelerate to normal speed. Type 0 (zero) to start moving the title at normal speed. To accelerate more gradually, specify more frames.
 - For Ramp Down, specify how many frames the clip should use to decelerate to a halt. For faster deceleration, specify fewer frames. Type 0 (zero) to stop the title immediately. To decelerate more gradually, specify more frames.
 - For Post Roll, specify how many frames you want the title to appear motionless (starting with the frame in which the title stops to the title Out point).

To preview rolling or crawling type:

Drag the slider at the bottom left corner of the Title window. Premiere plays back all rolling or crawling text objects in the Title window. If you have imported a background frame (see “Creating and setting up a new title” on page 275), Premiere uses the clip containing the background frame as the duration for the rolling or crawling type, and plays it along with the type.



Note: This slider does not preview special timings. Special timings depend on the clip duration in frames, which is determined by the Timeline. To preview special timings, add the title to a project Timeline (see “Adding a title to a project” on page 291) and preview the Timeline.

Creating graphic objects

The Title window toolbox contains tools for creating *graphic objects* such as straight lines, rectangles, ellipses, and polygons. Your polygons can have sharp, defined corners or you can smooth the corners into curves. Lines and shapes initially use the default line, color, gradient, and shadow attributes. When you change graphic attributes, the change affects all future items.

In the Title window, a graphic object can be either *framed* (outlined with no fill) or *filled* (filled with no outline). You can convert between framed and filled objects. If you want a shape to have both a fill and an outline, duplicate it and apply a fill to one and a line to the other.

To create a straight line:

- 1 Select the line tool in the toolbox (). Each tool reverts to the selection tool () after one use unless you double-click it, as explained in “Creating text objects” on page 278.
- 2 Drag to draw the line, or hold down Shift as you drag to draw a constrained line at 45-degree increments.

To create a rectangle, rounded-corner rectangle, or ellipse:

- 1 Click the left half of the desired tool for a framed shape or the right half of a tool for a filled shape.
- 2 Do one of the following:
 - Drag to draw the shape.
 - Hold down Shift as you drag to draw a constrained shape, such as a square, a rounded-corner square, or a circle.

To create a polygon shape:

- 1 Click the left half of the polygon tool () for a framed polygon, or click the right half of the polygon tool () for a filled polygon.
- 2 Position the polygon tool where you want to start drawing, and click. This creates a point and a line segment leading out of it.
- 3 Position the polygon tool where you want to end the line segment, and click.
- 4 Repeat steps 2 and 3 until you have only one segment left to draw.

5 Do one of the following:


- To close the polygon, click the first point you placed. A small circle appears next to the cursor when it is directly over the first point.
- To leave a framed polygon open, double-click where you want the last point to appear. You cannot leave a filled polygon open.

To change a filled object to a framed object or vice-versa:

- 1** With the selection tool, select the graphic object.
- 2** Choose Title > Convert to Filled or Title > Convert to Framed.

To adjust the line weight of a line or framed object:

- 1** With the selection tool, select the line or framed object that you want to change.
- 2** Drag the Line Weight slider to specify the line weight you want.



You cannot adjust the line weight of a filled object because it has no outline. However, you can create a framed duplicate of the object (see the next procedure) and adjust the line weight of the new object.

To create a framed duplicate of a filled object:

Select a filled object, and choose Title > Create Framed Object. A framed copy appears in the same position as the original.

To create a filled duplicate of a framed object:

Select a framed object, and choose Title > Create Filled Object. A filled copy appears in the same position on top of the original. If you can't see the framed original behind the filled copy, select the filled copy and choose Title > Send to Back.

To smooth a polygon:

- 1 With the selection tool, select a polygon.
- 2 Choose Title > Smooth Polygon.

To edit a polygon:


- 1 With the selection tool, select the graphic object that you want to edit.
- 2 Drag any handle on the object.

Adding a shadow

You can create an adjustable shadow for text or graphic objects. A slight shadow can help distinguish type from its background. However, a shadow tends to make small type less legible. You can apply color, transparency, or a gradient to a shadow. See “Using color, transparency, and gradients” on page 287.

To create a shadow:

- 1 Select the object to which you want to add a shadow.
- 2 Drag the Shadow Offset control in the toolbox to specify how far the shadow falls from the object. To constrain movement to 45-degree increments, hold down Shift as you drag.



Before (left) and after (right) adding a shadow

To specify the kind of shadow:

- 1 Select an object that has a shadow.
- 2 Choose Title > Shadow and choose a type of shadow from the Shadow menu:
 - Single creates a basic drop shadow.

- Solid simulates a three-dimensional shadow.
- Soft creates a soft-edged version of the Single shadow.

To remove a shadow:


- 1 Select an object that has a shadow.
- 2 Drag the Shadow Offset control either outside or to the center of the control area.
When the Shadow Offset control displays the message “No Shadow,” you have successfully removed it.

Using color, transparency, and gradients

You can apply color, transparency, gradient color, and gradient transparency to type, graphic objects, or shadows. You can also use the eyedropper tool to match a color that already exists in the Title window, even if it is in a background frame you imported.

To apply a solid color:

- 1 Do one of the following:
 - Use the selection tool (⌘) to select a text or graphic object to affect the entire object.
 - Use the type tool (T) to select individual characters in a text object to affect just those characters.
- 2 If necessary, click the Object Color swatch or the Shadow Color swatch to bring it to the front, and then click it again to open the color picker.



Object Color swatch (A) and Shadow Color swatch (B)

- 3 Specify a color (see “Using the color picker” on page 290), and click OK.

To match a color that exists in the title window:

- 1 With the selection tool, select a text or graphic object to which you will apply the color.
- 2 Select the eyedropper tool (.
- 3 Click the eyedropper tool on the color you want to apply.

To match a color and apply it to individual text characters:

- 1 Click in an area without objects to make sure that nothing is selected.
- 2 Select the eyedropper tool.
- 3 Click the eyedropper tool on the color you want to apply.
- 4 Click the Object Color swatch.
- 5 Write down the values for Red, Green, and Blue, and click Cancel.
- 6 Select the type tool and drag to select one or more text characters.
- 7 Click the Object Color or Shadow Color swatch, and for Red, Green, and Blue, type the values you wrote down. Then click OK.


To swap the object and shadow colors:

Click the curved double arrow (.

To apply a gradient:


- 1 Do one of the following:
 - Use the selection tool to select a text or graphic object (to affect the entire object).
 - Use the type tool to select individual characters in a text object (to affect just those characters).
- 2 If necessary, click the Object Color swatch or the Shadow Color swatch to bring it to the front. The swatch that is in front receives the gradient effect.

- 3 Click the Beginning Color swatch, specify a color (see “Using the color picker” on page 290), and click OK.



Beginning Color (A) and Ending Color (B) swatches

- 4 Click the Ending Color swatch, specify a color, and click OK.
- 5 To set the direction of a gradient, click a triangle in the Gradient/Transparency Direction option.



Clicking a triangle sets the direction of a gradient.

To set opacity:

- 1 Do one of the following:
 - Use the selection tool to select a text or graphic object (to affect the entire object).
 - Use the type tool to select individual characters in a text object (to affect just those characters).
- 2 If necessary, click the Object Color swatch or the Shadow Color swatch to bring it to the front. The swatch that is in front receives the opacity effect.
- 3 Do one of the following:
 - Click the triangle to the left of the Beginning Transparency menu or to the right of the Ending Transparency menu, and then click or drag in the menu that appears, to specify an opacity value.

- Click the triangle between the Beginning and Ending Transparency menus, and then click or drag in the menu that appears, to specify an opacity value from the Overall Transparency menu.

Using the color picker

In Premiere, you can specify color visually or using RGB (red, green, and blue) color values. The color picker becomes available whenever color is an option for a task you perform.

To use the Premiere color picker:

1 Do one of the following:

- To specify a color visually, click the color you want in the color area.
- To specify a color using RGB values, type the values you want into the Red, Green, and Blue options.

In the upper right corner of the color picker, the bottom half of the color swatch changes to display the color you specify. For reference, the top half of the color swatch displays the original color and does not change.

2 If a new color swatch appears with a gamut warning symbol (⚠) next to the lower color swatch, the color you specified is outside the *color gamut*, or range, that NTSC video can reproduce accurately. If you are editing for NTSC video, click the swatch or gamut warning symbol to automatically move the color to the nearest color within the NTSC color gamut when the title is rendered (its appearance does not immediately change). The gamut warning symbol does not apply to PAL and SECAM video, which have a larger color gamut.

3 Click OK.

Arranging text and graphic objects

By default, text and graphic objects appear in the window in the order in which they were drawn, from bottom layer to top layer. The Title window includes options for arranging text and graphic objects.

To arrange the stacking order of text and graphic objects:

- 1 With the selection tool (☞), select a text or graphic object.
- 2 Do one of the following:
 - Choose Title > Bring to Front.
 - Choose Title > Send to Back.
- 3 Repeat with other objects as necessary until type and objects are stacked the way you want.

To center type or objects in the drawing area:

- 1 With the selection tool (☞), select a text or graphic object.
- 2 Do any combination of the following as necessary to achieve the centering you want:
 - Choose Title > Center Horizontally.
 - Choose Title > Center Vertically.
 - Choose Title > Position in Lower Third.

Adding a title to a project

When you've completed and saved a title, Premiere automatically adds it to the open Project window. The title becomes a clip in the project, using the original title file as its source. If you imported a frame from a clip or a still image to use as a sample (see "Importing a sample frame" on page 275), it will not be part of the title when you add the title to a project. If you want to add a title that isn't currently open, import it the same way you would any other clip; see "Importing clips" on page 151.

If you want the title to display with transparency so you can superimpose it over another clip, add the title to a superimposition track. When you add a title to a superimposition track, empty and semitransparent areas of the title are converted into an *alpha channel*, which marks transparent and semitransparent areas. Premiere automatically applies the Alpha Channel transparency key to titles, making any mattes or clips on lower tracks visible under the title. Titles added to the Video 1A or 1B tracks appear opaque by default.

To add a title to a project:

1 Save the title. The title automatically appears in the open Project window.

Note: If a project is not open when you create the title, save the title, open a project, and then drag the title directly from the Title window to the Timeline or Project window.

2 Do one of the following:

- To superimpose the title over another clip, add it to a superimpose track (Video 2 or higher).
- To make the title appear opaque, add it to the Video 1A or 1B track (or select the Opaque option in the Title Window Options dialog box and add the title to any track).

Note: If you add a title to the Video 1A or 1B track and then move it to a superimposition track, it appears opaque. To make it transparent, delete it from the Timeline, and then add it directly to the superimposition track.

To change the duration of a title in the Timeline:

Do one of the following:

- Drag its In or Out point.
- Select it, choose Clip > Duration, and type a new duration.

To view a title with transparent areas:

Do one of the following:

- Render-scrub the portion of the Timeline that you want to view: press Alt (Windows) or Option (Mac OS) as you drag in the time ruler over the frames that you want to view.
- Build a preview of the title: in the Timeline, move the yellow work area bar so that it covers the portion of the Timeline containing the title, and then press Enter (Windows) or Return (Mac OS) to build a preview file (see “Previewing a video program” on page 227).

Note: If the background does not become transparent, double-click the clip in the Timeline to open it, choose Window > Title Window Options, and make sure that Opaque is not selected.



To change the duration of a title in the Timeline, drag its In or Out point, or select the clip, choose Clip > Duration, and type a new duration.

http://



7



Chapter 7: Superimposing and Compositing

You can create full or partial transparency in any clip in the Video 2 and higher tracks. You can also adjust the opacity of part or all of a clip, and you can superimpose clips on top of one another for special effects, transitions, or to add different backgrounds.

About transparency

In video or film, transparency allows one clip to show through another, creating composites, transitions, or special effects. The opacity of a clip or portion of a clip determines its level of transparency. At 100% opacity, an image contains no transparency at all; at 0% opacity, the image is completely transparent, allowing other clips to show through. At other percentages, the image is partially transparent, allowing other underlying images to be visible at the same time. The brightness values of a clip's *alpha channel*, an additional grayscale or monochrome channel in an RGB image, also determine the clip's opacity.

Certain parts of clips can be made transparent using tools called *keys*. A key finds pixels in an image that match a specified color or brightness and makes those pixels transparent or semitransparent, depending on the type of key. This process is called *keying*, or *keying out* the color. Keys can also use a clip's alpha channel to create transparency.

You can create transparency in a clip only after you have placed it in a superimpose track. By default, each new project includes one superimpose track, called Video 2. You can add up to 97 superimpose tracks. See “Adding, naming, and deleting tracks” on page 177.

Compositing

Special effects for film or video are often created by shooting a scene against a color screen. After the footage is digitized, the color screen is then made transparent with a key. The first scene, or clip, is placed over a second clip, which usually includes some sort of background scene. The result forms a composite, where the background is visible wherever the first clip is transparent, making the first clip appear to belong with the background.

Composites are often used in feature films where, for example, an actor appears to dangle from a helicopter or appears to be floating in outer space. In this case, the actor is shot in an appropriate position against a color screen, and after making the color transparent, the actor's scene is superimposed over the backdrop. Color screens are usually blue or green because these colors are relatively absent from skin or hair color.

Fading

In addition to making portions of a clip transparent with keys, you can also adjust the opacity of the entire clip to fade it in or out. You can use fading to create additional transitional effects or to create simple superimposing.

Using the Video Opacity rubberband


When you place a clip in a superimpose track, an *Opacity rubberband*, appears beneath it (you must expand the superimpose track to display the Opacity rubberband). The Opacity rubberband specifies the opacity of the entire clip. By adding handles, you can adjust the opacity of a clip.

The Opacity rubberband adjusts opacity after any keys have been applied. In other words, moving the Opacity rubberband adjusts the opacity for opaque, transparent, and semitransparent regions in the clip.

To adjust fading:

- 1 Place a clip in a superimpose track. If necessary, click the triangle to the left of the track name to expand the track, or Option-click (Mac OS) or Alt-click (Windows) the triangle to expand all the superimpose tracks at once.
- 2 Click the red Display Opacity Rubberbands icon (■) to display the opacity rubberband.
- 3 With the selection tool selected, position the pointer over the top of the Opacity rubberband. The pointer changes to a pointing finger with red plus (+) and minus (-) signs.
- 4 Click to create a handle (a small red square), and drag the handle up or down to adjust the fading. The opacity percentage appears in the Info palette and updates as you drag a handle. Press the Shift key with a handle selected to view the opacity percentage and to change the percentage in 1% increments for finer gradations.

When the handle is at the top of the panel, the image is fully opaque; when the handle is at the bottom of the panel, the image is transparent. The line between two handles indicates the direction, length, and speed of the adjustment. The steeper the angle, the more sudden the change.




Clicking the Opacity rubberband to create an opacity handle (left) and dragging it to decrease opacity (right)

- 5 Repeat the above step to create as many handles as needed.
- 6 To delete a handle, drag it out of the superimpose track.

To create two opacity handles:

- 1 Select the fade scissors tool (>✂).



- 2 Click the Opacity rubberband where no handles exist. Two adjacent handles appear.
- 3 Drag the new handles up or down to make a sharp increase or decrease in opacity.

To adjust the opacity of a specific segment:

- 1 Select the fade adjustment tool (⊕).



- 2 Drag the line segment up or down. You can set the opacity of the entire clip to a constant value by adjusting the opacity rubberband in this manner before creating handles.


Using keys to superimpose and create composites

Adobe Premiere provides 15 *keys* (methods for creating transparency) that you can apply to a clip to create transparency in many different ways. You can use color-based keys for superimposing, brightness keys for adding texture or special effects, alpha channel keys for clips or images already containing an alpha channel, and matte keys for adding traveling mattes or creative superimpositions.

In some cases, you can make keying easier by using a temporary brightly colored background matte. A bright color underneath the image you are keying makes it easier to see areas of transparency. See “Adding a background matte” on page 306.

To apply a key to a clip:

- 1 Select the clip in a superimpose track (Video 2 or higher).
- 2 Do one of the following:
 - In the Effect Controls palette, click Setup next to Transparency.
 - Choose Clip > Video Options > Transparency.
- 3 Choose a key from the Key Type menu.



The default key type is None. At this setting, no part of the superimposed image is keyed out. However, you can set the opacity of the image by adjusting the opacity rubberband in the Timeline (see “Using the Video Opacity rubberband” on page 296). You can also use the None key type for creating split screens and other effects where a portion of the underlying image is visible (see “Creating split screens” on page 308).

4 Click one of the following icons to view transparency:

- Places a black or white background behind the keyed-out image. Click to toggle between black and white.
- Displays a checkerboard pattern to help you view transparency in areas that may be difficult to see against a solid background or against the actual underlying image. Click to reverse the checkerboard pattern.
- Displays the actual underlying image in your project. This view may be slower to display when you drag the preview slider under the Sample box.

5 To zoom in on the image in the Sample area, select the Zoom icon (⌕), and then click an area of the image. Click again to increase the zoom. To zoom out, hold down the Alt key (Windows) or the Option key (Mac OS) and click the image with the Zoom icon selected. To view other areas of the image at the same zoom, select the Hand icon (☞) and drag the image. On Mac OS only, you can click the Collapse icon (⌵) to move the image to the Program view in the Monitor window.

6 Select the following options as needed:

- Reverse Key to reverse transparent and opaque areas (available only for certain keys).
- Drop Shadow to add a 50% gray, 50% opaque shadow to opaque areas (available only for certain keys). The shadow is placed four pixels below and to the right of any contiguous opaque region. Drop Shadow is most effective for titles or simple graphics.
- Mask Only to produce a special effect that displays only the alpha channel matte view of the clip (available only for certain keys).

7 Adjust the transparency sliders and select other options as described in the following sections on individual keys.

8 Drag the slider beneath the Sample box to view your transparency settings across the duration of the clip.

9 Click OK to apply the settings to the clip.

Note: You can quickly access the transparency settings for a clip by clicking Setup next to Transparency in the Effect Controls palette.

Using the Chroma key type

Use the Chroma key to select a color or a range of colors in the clip to be transparent. You can use this key when you have shot a scene against a screen that contains a range of one color, such as a shadowy blue screen. Select a key color by clicking the color swatch or by using the eyedropper to choose a color from the thumbnail beneath the color swatch; use the slider bars in the dialog box to adjust the color that you want to key out.

Adjust the following Chroma key settings as necessary:

Similarity Broadens or reduces the range of color that will be made transparent. Higher values increase the range.

Blend Blends the clip you are keying out with the underlying clip. Higher values blend more of the clip.

Threshold Controls the amount of shadows in the range of color you keyed out. Higher values retain more shadows.

Cutoff Darkens or lightens shadows. Drag to the right to darken shadows, but do not drag beyond the Threshold slider; doing so inverts gray and transparent pixels.

Smoothing Specifies the amount of anti-aliasing that Premiere applies to the boundary between transparent and opaque regions. Anti-aliasing blends pixels to produce softer, smoother edges. Choose None to produce sharp edges, with no anti-aliasing. This is useful when you want to preserve sharp lines, such as those in titles. Choose Low or High to produce different amounts of smoothing.

Using the RGB Difference key

The RGB Difference key is a simpler version of the Chroma key. You can select a range of color, but you cannot blend the image or adjust transparency in grays. Use the RGB Difference key for a scene that is brightly lit and contains no shadows, or for rough cuts that don't require fine adjustments. Select a key color by clicking the color swatch or by using the eyedropper to choose a color from the thumbnail beneath the color swatch.

Adjust the following RGB Difference key settings as necessary:

Similarity Broadens or reduces the range of color that will be made transparent. Higher values increase the range.

Smoothing Specifies the amount of anti-aliasing (softening) that Premiere applies to the boundary between transparent and opaque regions. Choose None to produce sharp edges, with no anti-aliasing. This is useful when you want to preserve sharp lines, such as those in titles. Choose Low or High to produce different amounts of smoothing.

Using the Blue Screen and Green Screen keys

The Blue Screen and Green Screen keys create transparency from true chroma blue and true chroma green. Use these keys to key out well-lit blue or green screens when creating composites.

Adjust the following Blue Screen and Green Screen key settings as necessary:

Threshold Drag to the left until the blue or green screen is made transparent.

Cutoff Drag to the right until the opaque area reaches a satisfactory level.



To fine-tune edges, drag Threshold and Cutoff sliders in small increments.

Using the Non-Red key

The Non-Red key creates transparency from green or blue backgrounds. It is similar to the Blue Screen and Green Screen keys, but it also lets you blend two clips. In addition, it helps reduce fringing around the edges of nontransparent objects. The Non-Red key is recommended for keying out green screens when you need to control blending, or for when you are not able to produce satisfactory results with the Blue Screen or Green Screen keys.

Adjust the following settings as necessary:

Threshold Drag to the left until the blue or green screen is made transparent.

Cutoff Drag to the right until the opaque area reaches a satisfactory level.

Blend Drag to blend the image with any underlying image.

Using the Luminance key

The Luminance key creates transparency for darker values in the image, leaving brighter colors opaque. Like the Multiply and Screen keys, it is most effective when the image that you are keying contains highly contrasting dark and light areas. Use the Luminance key to create a subtle superimposition or to key out dark areas.

Adjust the following settings as necessary:

Threshold Specifies the range of darker values that will become transparent. Higher values increase the range of transparency.

Cutoff Sets the opacity of areas that have been specified by the Threshold slider. Higher values increase transparency.

Using the Multiply and Screen keys

The Multiply and Screen keys use an underlying image as a map to determine what part of the keyed image to make transparent. The Multiply key creates transparency in the areas of the image that correspond to the bright areas in the underlying image. Conversely, the Screen key creates transparency in the areas that correspond to the dark areas of the underlying image. Use these keys to create a subtle superimposition, when the underlying image contains highly contrasting elements.


Adjust the following setting as necessary:

Cutoff Drag to the right until the opaque area reaches a satisfactory level. Higher values produce less transparency.

Using the Alpha Channel key

Images represented on video are composed of three grayscale images called *channels*—one red, one green, and one blue. Such images are called *RGB images*. An *alpha channel* is a fourth channel in an RGB image that defines what parts of the image are transparent or semitransparent. Many programs, such as Adobe Illustrator and Photoshop, use alpha channels so that you can specify transparent regions in an image. An alpha channel is either *straight* or *premultiplied*, depending on the program that created the image. When an image contains a straight alpha channel, the transparency information is stored only in the alpha channel. When an image contains a premultiplied alpha channel, the background color that is intended to be transparent is also blended into the edges of an image. Use the Alpha Channel key on clips that contain a straight alpha channel, such as images created in Adobe Photoshop, Adobe Illustrator, and Adobe After Effects.

When you use the Alpha Channel key with a clip to which you have applied or plan to apply motion, select the Use Clip's Alpha option in the Motion Settings dialog box. If this setting is not selected, the clip's bounding box will appear when the clip moves. See “Specifying alpha channel and color options” on page 318.



The Photoshop image (left) contains a separate alpha channel (center) which Premiere uses to superimpose the foreground on another background (right).

Using Black Alpha Matte and White Alpha Matte keys

Typically, an image that contains a premultiplied alpha channel also contains either a black or white background. If you are superimposing the image, you likely need to key out the background.

To key out a black background, use the Black Alpha Matte; to key out a white background, use the White Alpha Matte.

Image Matte

The Image Matte key uses a specified still image (the *matte*) to determine the areas of transparency for a clip. Areas in the superimposed clip that correspond to areas of white in the still image remain opaque, areas of black in the still image become fully transparent in the clip, and areas in the image that are between white and black produce varying levels of transparency in the clip.

To get the most predictable results, choose a grayscale image for your image matte, unless you want to alter colors in the clip. Any color in the image matte removes the same level of color from the clip you are keying. For example, white areas in the clip that correspond to red areas in the image matte will appear blue-green (since white in an RGB image is composed of 100% red, 100% blue, and 100% green); because red is also made transparent in the clip, only blue and green colors would remain at their original values.

Adjust the following Image Matte settings as necessary:

Choose Click to select an image. Portions of the clip in the superimpose track that correspond to the white areas of the image are superimposed on clips in lower tracks. The image acts as a filter between the clips.

Reverse Key Click to reverse transparency. Portions of the clip in the superimpose track that correspond to the black areas of the image are superimposed on clips in lower tracks.

Difference Matte

The Difference Matte creates transparency by comparing a specified image with a specified clip and then eliminating areas in the clip that match those in the image. Though you can use this key to create special effects, you can also use it to key out a static background by selecting the Reverse Key option.

In this way, you can remove a static background behind a moving object (such as a person walking past a stage set), and place the person against a different background. Very often the specified image is simply a frame of background footage (before the moving object has entered the scene). For this reason, the Difference Matte is best used in this way for scenes that have been shot with a stationary camera.

To replace a static background behind a moving object:

- 1 Find a frame of your clip that consists only of the static background.
- 2 Save this background frame as an image file. For information about saving a frame, see “Exporting a still image” on page 347.
- 3 Place the video clip in a superimpose track, select it, and then choose Clip > Video Options > Transparency.
- 4 For Key Type, choose Difference Matte.
- 5 In the Matte section of the dialog box, click the Choose button and select the image you saved in step 2.
- 6 Select the Reverse Key option to key out the static background.
- 7 Place the new background in a track below this one to create the composite.

Track Matte

Use the Track Matte key to create a moving matte (often called a *traveling matte*), which superimposes one clip on another using the matte to integrate the two. You can use any clip, still image, or still image with motion for the matte.



Because the Track Matte key can be applied to a video clip, the matte can change over time.

Areas of white in the matte create opaque areas in the superimposed clip, preventing underlying clips from showing through. Black areas in the matte create transparent areas, and gray areas make partially transparent areas. To retain the original colors in your superimposed clip, use a grayscale image for the matte. Any color in the matte removes the same level of color from the superimposed clip.

You can create mattes in a few different ways:

- Use the Title window to create text or shapes (grayscale only), save the title, and then import the file as your matte.
- Create a matte from any clip using the Chroma, RGB Difference, Difference Matte, Blue Screen, Green Screen, or Non-Red key. Then select the Mask Only option.
- Use Adobe Illustrator or Photoshop to create a grayscale image, import it into Premiere, and (optionally) apply motion settings to the image.
- Add motion to any still image with the Motion settings in Premiere. For information on applying motion to still images, see “Animating a clip’s motion” on page 311.

To apply the Track Matte key:

- 1** In the Video 1 track, place the clip that will play in the background.
- 2** In the first superimpose track, Video 2, place the clip that will be superimposed on the clip in the Video 1 track.

- 3 If the Timeline window already contains a second superimpose track, go on to step 4. If not, click the Timeline menu icon and choose Add Video Track.
- 4 In the second superimpose track, Video 3, place the clip or image you want to use as the matte.
- 5 Select the clip in the Video 2 track and choose Clip > Video Options > Transparency. For Key Type, choose Track Matte. Then click OK.

Superimposing two or more clips

You can superimpose several clips one on top of another in up to 97 superimpose tracks. Each clip must be on a separate superimpose track. You can also rename each track with descriptive names. For details, see “Adding, naming, and deleting tracks” on page 177.

Adding a background matte

You can create a full-frame matte of a solid color that you can use like a clip. You can use mattes, for example, as a solid background for titles. Brightly colored mattes can serve as temporary backgrounds while you use a key to help you see transparency more clearly.

To create a background matte:

- 1 Activate the Project window.
- 2 Choose File > New > Color Matte.
- 3 Select a color from the Color Picker window and click OK.
- 4 Type a name for the matte, as you want it to appear in the Project window. Then click OK.



Create a backdrop from an existing frame by exporting a frame as a still image. See “Exporting a still image” on page 347.

To use a temporary matte for keying:

- 1 Create a background matte as described above. Typically, a bright green or yellow works best.
- 2 Place the matte in a track beneath the clip you are keying, in either a superimpose track or the Video 1 track.

- 3 Make the matte the same length as the clip you are keying so that you can preview transparency across the entire clip.
- 4 Create transparency in the clip as described in “Using keys to superimpose and create composites” on page 298. The brightly colored matte shows through in the areas that are transparent.
- 5 When you are satisfied with your keying, delete the colored matte from the Timeline window.

Creating garbage mattes

Sometimes the subject of a scene is properly keyed except for undesired objects. Use a *garbage matte* to mask out those objects. You can then place the keyed subject in another scene for simple effects.



The microphone (left) is masked out by repositioning image handles in the Transparency dialog box (center), creating a garbage matte that is then keyed and superimposed over a background (right).

To create a garbage matte:

- 1 Select a clip in a superimpose track and choose Clip > Video Options > Transparency. For more details, see “Using keys to superimpose and create composites” on page 298.
- 2 In the Sample area of the Transparency Settings dialog box, drag the handles of the image to include only the subject you want to preserve.
- 3 Choose a key to key out the background of your subject. Then click OK.

Creating split screens

Use the Transparency Settings to create a split screen or other types of screen effects that show two clips side by side.

To create a split screen:

- 1 Place two clips in separate adjacent tracks. At least one track must be a superimpose track.
- 2 Select the clip in the upper track and choose Clip > Video Options > Transparency.
- 3 For Key Type, choose None.
- 4 Drag the corner handles in the Sample area to split or otherwise separate the screen into two sections, one containing the clip in the upper track, the other containing the clip in the lower track.
- 5 To view the effect, click the page peel icon (). Then click OK.

http://



8




Chapter 8: Animating a Clip

You can move, rotate, and zoom a video or still-image clip within a video program's viewable area. Using the settings in the Motion Settings dialog box, you can specify a motion path, change motion over time with keyframes, and speed up or slow down the motion you've defined. In addition, you can distort the shape of a clip to create other special effects.

Animating a clip's motion

Animate a clip by creating a motion path in the Motion Settings dialog box. You can specify the path completely within the visible area, or extend it beyond so that the clip enters and exits at the boundaries. Note that you can add motion only to the clip itself, as a whole; you cannot add motion to elements within the clip. In addition, you can specify rotation, zooming, delays, and distortion to create more complex motion. See “Rotating, zooming, delaying, and distorting” on page 316.


Note: You can also animate a clip using the Transform effect. For more information, see *online Help*.



A. Preview window B. Motion path C. Motion timeline

To define a motion path for a clip:


- 1 Select a clip in the Timeline window.
- 2 Do one of the following to open the Motion Settings dialog box:
 - Click the box to the left of the word Motion in the Effect Controls palette.



- Choose Clip > Video Options > Motion.

In the top left corner of the dialog box, a sample of the selected clip moves along the default motion path. To the right of the sample is the motion path. The default path locates the Start and Finish keyframes outside the viewable area of the video program so that the clip enters the viewable area from the left, moves across, and exits on the right.

- 3 Set and adjust keyframes on the motion path using one of the following methods:
 - For simple horizontal, vertical, or diagonal motion, drag the Start and Finish keyframes to any location within or outside the visible area.
 - Position the pointer anywhere on the motion path. The pointer turns into a pointing finger. Click to add a keyframe to the path, and drag to adjust its position, creating a new segment of the path.



Click to make a motion keyframe (left), and then drag the keyframe to a new location (right).

- Click above the motion path timeline (located directly below the motion path) to add a keyframe to the path; the pointer turns into a downward-pointing triangle (▼). Then drag the new keyframe to adjust its position.

4 To preview the animation, use the Play (▶) and Pause (⏸) buttons. For other preview options, see “Previewing motion” on page 315.

To fine-tune the position of a keyframe on the motion path:

1 Select the keyframe using either method below:

- Click the keyframe in the motion path or in the motion path timeline. The pointer turns into a gray pointing-finger icon when it is directly over a keyframe.
- Press the Tab key to select successive keyframes from the Start to Finish positions along the motion path. Hold down the Shift key and press Tab to move from keyframe to keyframe in the opposite direction.

***Note:** If a text entry box is active in the Motion Settings dialog box, pressing Tab highlights successive boxes rather than selecting successive motion keyframes.*

2 Use one of the following methods to adjust the keyframe’s position:

- Press an arrow key to move the selected keyframe 1 pixel at a time in the direction of the arrow.
- Hold down the Shift key and press an arrow key to move the keyframe in 5-pixel increments.
- Type coordinates for the keyframe’s position in the Info boxes below the timeline.

***Note:** In the Motion Settings dialog box, the coordinates in the Info boxes are specified at the resolution of the sample image (80 x 60 pixels), but are scaled at output time to the project output size. A 1-pixel shift at the sample size scales up to a 4-pixel shift if the project output size is 320 x 240 or to an 8-pixel shift if the output size is 640 x 480. You can type fractional decimal values to reposition keyframes with finer precision than 4- or 8-point increments. For example, typing 1.75 in the first box results in a horizontal shift of 14 pixels at 640 x 480 resolution. To derive the correct value to type for the direction you want to move, first divide the appropriate output dimension (for example, 640) by the corresponding sample image dimension (80), and then divide the distance you want to move (for example, 14 pixels) by the result.*

To center the clip in the viewable area at a keyframe on the motion path:


- 1 Select the keyframe.
- 2 Type the coordinates (0, 0) for the keyframe's position in the Info boxes below the timeline, or click the Center button to let Adobe Premiere enter these coordinates.

To delete a keyframe on the motion path:

Select the keyframe and press Delete.

To edit motion settings for a clip:

- 1 In the Timeline window, select the clip with the motion settings you want to edit.
- 2 Do one of the following:
 - In the Effect Controls palette, click Setup next to Motion.



- Choose Clip > Video Options > Motion.
- 3 Edit the settings, and then click OK.

Changing the speed of motion

You can change the speed of motion by positioning motion keyframes along the timeline. Keyframes that have been added to the motion path are represented on the timeline below the path. The length of the timeline represents the duration of the clip.

The timeline also includes a control for specifying the view of time. Clicking the two red arrows to the right of the timeline toggles between the source clip's time display and the Timeline window's time display. Use this control to synchronize motion or specify motion at an exact point in time. See "Specifying an exact time for motion" on page 317.

To change the speed of the motion:

- 1 Select the motion keyframe in either the path or the timeline in the Motion Settings dialog box. You can also press Tab or Shift+Tab to select each motion keyframe in succession. A black downward arrow indicates which keyframe is selected in the timeline.
- 2 Drag the arrow to the left or right. Dragging the arrow closer to another motion keyframe increases the speed between the two keyframes; dragging it farther away from a keyframe decreases the speed between the keyframes.

To smooth sharp changes in direction, rotation, and distortion:

Click Smooth Motion and choose a smoothing option. Smooth Motion provides the smallest amount of smoothing, and Averaging-High provides the greatest amount of smoothing.

Previewing motion

The motion settings are applied to the sample in the upper left corner of the Motion Settings dialog box, so that you can preview any changes you make.

To preview motion in the Motion Settings dialog box:

Do any of the following:

- Click the Play button (▶) next to the motion thumbnail. Click the Pause button (⏸) to pause the preview.
- Drag the upward-pointing arrow along the motion timeline.
- On Mac OS only, click the Collapse icon (⌵) to move a still preview to the Program view in the Monitor window. Use this option to see where the image appears within the viewable area at different position points on the motion path. Click the Uncollapse icon (⌶) to move the preview back to the Motion Settings dialog box.
- Select Show All to display the image along the motion path as it would appear in the final video program, including transitions, filters, and transparency settings. Note that the motion thumbnail may not play as smoothly with this option selected.
- Select Show Outlines to display an outline of the clip (including any rotation, zooming, or distortion) at each motion keyframe in the path.
- Select Show Path to display the motion path as a series of dots between the motion keyframes. Dots closer together indicate a slower speed; dots farther apart indicate a faster speed.

To preview motion in the Monitor window:

- 1 Click OK to save and close the motion settings.
- 2 Do one of the following:
 - Build a preview file: move the yellow work area bar so it covers the clip with the motion settings and press Enter (Windows) or Return (Mac OS).
 - Render-scrub the area you want to preview: hold down Alt (Windows) or Option (Mac OS); when the cursor becomes a downward pointing arrow (⏏), scrub in the Timeline window's time ruler.

Rotating, zooming, delaying, and distorting

For each motion keyframe on the path, you can set values for rotation, zoom, and delay, and define a shape for distorting the clip. By specifying different values at different motion keyframes, you can rotate, zoom, delay, and distort the clip over time.

To rotate, zoom, or delay the clip:

- 1 On the motion path or the timeline in the Motion Settings dialog box, select the motion keyframe at which you want to add rotation, zooming, or distortion.
- 2 Drag the slider or type a value for the following controls as needed:
 - For Rotation, set the angle of rotation for a clip at the specified keyframe. The angle can range from -1440 degrees to 1440 degrees, resulting in up to eight full rotations (clockwise or counterclockwise) of the clip between keyframes. (One full rotation is equal to 360 degrees.)
 - For Zoom, increase or decrease the size of a clip at a specific keyframe on the motion path. The zoom percentage can range from 0 to 500. At 0, the clip is not visible; at 100, the clip is at its original size.
 - For Delay, direct the motion of a clip to pause for the specified amount of time. The delay value is a percentage of the duration of the clip. A delay percentage cannot exceed the distance in time to the next motion keyframe. When a delay has been added, a blue bar appears on the timeline, displaying the length of the delay.

3 Choose an option from the Motion menu to define how the motion should occur between the selected keyframe and the next keyframe. You can achieve smooth motion when zooming by speeding up or slowing down movement where necessary. When zooming from small to large, select Accelerate. When zooming from large to small, select Decelerate.

4 Repeat steps 1 to 3 for each motion keyframe you want to change.

***Note:** Use the normal keyboard shortcuts for copying and pasting work when you copy one keyframe's motion settings to another keyframe in the same clip or in another clip.*

To distort a clip:

1 In the motion path or timeline in the Motion Settings dialog box, select the keyframe at which you want to add distortion.

2 In the distortion area, do any of the following:

- To create distortion, drag one or more of the four corner points to other positions.
- To spin a distorted image around a center point, hold down the Alt key (Windows) or the Option key (Mac OS) and position the pointer on a corner point; then drag to spin the image around a center point.
- To move all four corner points at once, position the pointer in the center of the image and drag.

3 Repeat steps 1 and 2 for each motion keyframe that you want to distort.

Specifying an exact time for motion

To synchronize motion with other events in your video program, or to specify an exact time for motion, use the time display next to the motion timeline. The time display shows the time of the selected motion keyframe, as measured from either the beginning of the clip, or from the beginning of the entire video program.

To specify an exact time for motion:

- 1 Click the two red arrows next to the time display to specify how time is measured:
 - If the two arrows touch, , the time is measured using the clip's duration. So, if the clip is 20 seconds long and you set a keyframe at 00:10:00, the keyframe appears halfway through the clip's duration. Use this option to specify an exact location in the *clip* for the keyframe.
 - If the two arrows are separated, , the time is measured using the entire duration of the video program in the Timeline window. So, if the clip is located at 00:10:00 in the video program, and it is 20 seconds long, you can specify an exact location between 00:10:00 and 00:30:00 in the Timeline to position the keyframes.
- 2 Create a motion keyframe by clicking in the motion timeline (or by selecting an existing one). Then drag it to the appropriate time by watching the time display.

Specifying alpha channel and color options

You can include a fill color and specify how Premiere treats the alpha channel of the clip.

In the Motion Settings dialog box, choose any of the following options:

Reset Removes the distortion, delay, rotation, and zoom settings for a selected keyframe.

Fill Color Specifies a background color that fills the frame behind the moving clip. To select a background color, click the desired color on the thumbnail in the Fill Color box (the pointer turns into the eyedropper tool when it is on the thumbnail), or click the color swatch above the thumbnail to access the color picker and choose a color. This color appears in previews and the rendered video program only if the clip is placed in the Video 1 track.

Alpha: Use Clip's Superimposes a clip using its existing alpha channel. This is the normal setting for titles or graphics created in another application that supports alpha channels, such as Adobe Photoshop. This option affects only those clips that have been assigned an alpha channel key type in the Transparency Settings dialog box. For information on alpha channels, see “Using the Alpha Channel key” on page 302.

Alpha: Create New Creates a transparent fill for clips that do not have an existing alpha channel. With this option selected, an alpha channel is created for the areas in the clip that have been assigned a key type in the Transparency Settings dialog box. See “Using the Alpha Channel key” on page 302.

***Note:** Choosing the Create New option for an image containing an alpha channel overwrites the original alpha channel when the image is superimposed.*

Saving, loading, and deleting motion settings

Use the Save and Load buttons in the Motion Settings dialog box to save the motion settings you create for a clip for later use with other clips. Motion settings are applied to entire clips; they cannot be applied to a limited number of frames of a clip.

To remove all motion settings applied to a clip, click Remove in the Motion Settings dialog box.

http://



9



Chapter 9: Applying Effects

Adobe Premiere includes a variety of audio and video effects that you can apply to clips in your video program. An effect can add a special visual or audio characteristic or provide an unusual feature. For example, an effect can alter the exposure or color of footage, manipulate sound, distort images, or add artistic effects. The intensity and position of an effect are determined by values that you control.

You can add any effect to a clip at any time. If you don't like an effect, you can easily delete it. You can even apply the same effect multiple times to the same clip with different settings. For example, you can add multiple instances of the Equalize audio effect for situations when you would chain together multiple equalization hardware modules in a conventional audio studio.

By default, when you apply an effect to a clip, the effect is active for the duration of the clip. However, you can make the effect start and stop at specific times, or make the effect more or less intense over time, by using keyframes.

Understanding keyframes


Premiere uses *keyframes* to change an effect over time. A keyframe contains the values for all the controls in the effect and applies those values to the clip at the specified time. By default, once you apply an effect to a clip, Premiere creates a beginning and ending keyframe with the same value, but by applying different values to keyframes, you can change an effect over time. Premiere automatically interpolates the values of the controls between the keyframes, using a linear progression. This means that you don't have to create a keyframe for every frame in the clip.

For example, suppose that you wanted to use the Crystallize effect and have it increase and then decrease over time. In this case, you would need to set three keyframes—the first with light crystallization, the second with more significant crystallization, and the third with light crystallization. Because Premiere automatically interpolates the distortion between each keyframe, the crystallization will gradually increase (linearly) between the first and second keyframes and then gradually decrease between the second and third keyframes.


Note: *Some Premiere effects are not keyframeable and cannot be animated.*

Working with keyframes

To modify effect settings with keyframes, create keyframes in the keyframe line of the Timeline window. You can then adjust the effect's controls for each keyframe in the Effect Controls palette.



A. Effect keyframe button B. Keyframe navigator C. Effect pop-up menu
D. Keyframe line



A. Effect Enabled button with the stopwatch icon visible
B. Keyframing Enabled button
C. Effect name D. Effect controls

Keyframe line

After you add an effect to a clip, the effect appears under the clip in the keyframe line in the Timeline window. When you add more than one effect to a clip, the effect pop-up menu appears at the left edge of the clip. This menu displays each of the applied effects. If the effect has adjustable controls, you can set keyframes for it in the keyframe line. The keyframe line for any video clip on the Video 2 or above tracks can display either effect (◊) or opacity handles (■). The keyframe line for an audio file can display effect, volume, or pan (■) keyframes. To display effect keyframes for either type of clip, click the effect keyframe button (◊).

Note: When the Video 1 track is collapsed, displaying both the A and B track on one line, Premiere displays the keyframe line for the Video 1 A track, or for the selected clip.

Keyframe navigator

After you set the initial keyframe for a clip, and if the keyframe button is pressed, Premiere displays the keyframe navigator, which you can use to move from keyframe to keyframe or to set or remove keyframes. A checkmark in the keyframe navigator box indicates that the edit line lies precisely at a keyframe for that clip. When the box contains no checkmark, the edit line lies between keyframes.

Keyframe icons

The appearance of a keyframe icon depends on where it is on the track. The default (first and last) keyframes are white rectangles (■) that rest at the edges of the clip. Once you add additional keyframes (◊), the initial keyframes become white half-diamonds. Once you move the keyframes from the edges, they become full diamonds. The first keyframe is gray on the left half (◊), and the last keyframe is gray on the right half (◊).

Effect Enabled button

When you create a keyframe for an effect, a stopwatch icon (⌚) appears in the Effect Enabled button next to the effect name in the Effect Controls palette. Once the stopwatch appears for a specific effect, Premiere automatically sets new keyframes whenever you move the edit line and change the effect's controls. Clicking the Effect Enabled button again, which removes the stopwatch, deletes all keyframes, except the default keyframes. Setting a value for an effect control when the stopwatch has been removed modifies the default (first and last) keyframes, and that value remains in effect for the duration of the clip.

Working with effects

When you apply an effect to a clip, the effect is listed in the Effect Controls palette. The effect is also listed directly above the clip's keyframe line. If a clip has multiple effects applied, the effect pop-up menu lists them and they are rendered in order from top to bottom in this list. You can reorder the effects in this list to change which effects are rendered first. See the procedure “To reorder effects” in “Applying and controlling effects” on page 327 for information on changing the render order.



For a list of and information about each effect and its options, see online Help.

Using the Audio and Video Effects palettes

All effects are stored in the Audio or Video Effects palette, which you can customize to best suit your working style. Effects are grouped by type; for example, all video effects that create a blur are listed in a Blurs folder in the Video Effects palette. You can hide effects that you don't use and create new folders containing special groups of commonly used effects or rarely used effects.



To open an effects palette:

Do one of the following:

- Choose Window > Show Video Effects.
- Choose Window > Show Audio Effects.

To create a new folder in the Video or Audio Effects palette:

1 Open the palette and do one of the following:

- Choose New Folder from the Effects palette menu.
- Click the New Folder button (□) at the bottom of the palette.

2 Type a name for the folder and click OK.

To delete a folder:

Select the folder and do one of the following:

- Choose Delete Folder from the Effects palette menu.
- Click the Delete button (🗑) at the bottom of the palette.

***Note:** If you delete a default folder, the folder and all its effects are hidden and moved to the bottom of the palette. If you delete a custom folder (one you created), the folder is deleted and all its effects are restored to their original folders and hidden.*

To hide folders or effects:

- 1** Select the folder or the effects. Shift-click to select multiple contiguous effects or Command-click (Mac OS) or Control-click (Windows) click to select multiple noncontiguous effects.
- 2** Choose Hide Selected from the Effects palette menu. All selected effects and folder names are dimmed and, if Show Hidden in the Effects palette menu is deselected, the names are hidden.
- 3** To hide the dimmed names, if they were not hidden in the above step, choose Show Hidden from the Effects palette menu to deselect it.

To view hidden folders or effects:

- 1** Choose Show Hidden from the Effects palette menu. All folders and effects that were hidden now appear dimmed.
- 2** Select the dimmed folders or effects that you want to make active and choose Show Selected from the Effects palette menu.

To move effects from one folder to another:

- 1** Drag the effect name to the desired location.
- 2** Release the mouse when the desired location is highlighted.

Applying and controlling effects

You can apply a video effect to a video clip in the Video 1 track and in any superimpose track. You can also apply an audio effect to any audio clip in the Timeline window. Clips that have effects applied to them appear with a blue border at the top in the Timeline window.

You can apply or remove an effect at any time. Once you've applied effects to a clip, you can temporarily turn off one or all of the effects in the clip to concentrate on another aspect of your project. Effects that are turned off do not appear in the Program window and are not included when the clip is previewed or rendered. Turning off an effect does not delete the keyframes created for any of the effect's settings; all keyframes remain until the effect is deleted from the clip.

To apply an effect to a clip:

- 1 Choose Window > Show Video Effects or Window > Show Audio Effects.
- 2 In the Effects palette, select an effect and drag it to a clip in the Timeline Window, or if the clip is selected in the Timeline Window, drag the effect to the Effect Controls palette.
- 3 If the effect has controls, the Settings dialog box appears. The settings you choose here apply to the first keyframe (if you change settings for other keyframes) or to the entire clip (if you make no changes to any keyframe). Click OK to apply the settings.

Note: A Settings dialog box does not appear for After Effects effects. Instead, choose your settings for these effects in the Effect Controls palette.



Using this procedure, you can apply multiple instances of a single effect to a clip.

To open the Effect Controls palette:

Choose Window > Show Effect Controls.

To view a clip's effects in the Effect Controls palette:

Select the clip in the Timeline window.

To open the Settings dialog box for an effect:

In the Effect Controls palette, click Setup to the right of the effect name.

To copy an effect and its keyframes in a clip and paste it into another clip:

- 1 In the Effect Controls palette, select the effect and choose Edit > Copy.
- 2 In the Timeline window, select one or more clips and choose Edit > Paste Attributes.
- 3 In the Paste Attributes dialog box, select Settings; then deselect all options except Filters.

To temporarily turn off an effect:

In the Effect Controls palette, select the effect, and then click the Effect Enabled button() to the left of the effect name.

To remove an effect from a clip:

- 1 Select the clip in the Timeline window.
- 2 In the Effect Controls palette, select the effect you want to remove and do one of the following:
 - Click the Delete button ().
 - Choose Remove Selected Effect from the Effect Controls palette menu.

To reorder the effects:

- 1 In the Effect Controls palette, click on the triangle next to each effect to collapse the settings.
- 2 Click an effect name and drag it to a new location on the list. A black line appears while you drag when the effect is above or below another.


Using keyframes with effects

Each effect has a default keyframe at the beginning and end of the clip, indicated by half-diamonds on the keyframe line in the Timeline window. If an effect has adjustable controls, you can change the start or end time of the effect or add additional keyframes to create an animated effect. If you don't make any changes to the default keyframes, the settings for the associated effect apply to the entire clip.

Note: The pointer becomes a shaded finger when it is on a keyframe.

To set a keyframe for an effect:

1 In the Timeline window, click the triangle to the left of the track name to display the keyframe line.



2 If the clip is on a Video 2 or above track, click the effect keyframe icon (◆) to display effect keyframes.

3 If the clip contains more than one effect, click the effect pop-up menu above the keyframe line to the left of the effect's name and select an effect.

4 Position the edit line at the point where you want to create a keyframe and do one of the following:

- Adjust the effect settings in the Effect Controls palette.
- Select the clip and click the keyframe navigator box (□).

Note: Once you set the initial keyframe for an effect, the Effect Enabled icon (Ⓢ) appears next to the effect name in the Effect Controls palette.

To select a keyframe:

Click the keyframe icon on the keyframe line.

To move the edit line to the previous or next keyframe:

Select the clip containing the keyframe, and then press the forward or backward keyframe navigator arrow (◀ ▶).

To change an effect's settings at a keyframe:

- 1 Select a keyframe either by clicking it, using the keyframe navigator to move the edit line to it, or manually positioning the edit line on it.
- 2 In the Effect Controls window, select the effect and do one of the following:
 - Click Setup and make your changes in the Settings dialog box; then click OK.
 - Make your changes using the available settings controls. If effect settings are not visible, click the triangle next to the effect name to show them.

To remove a keyframe:

Select the keyframe in the effect keyframe line and do one of the following:

- Drag the keyframe outside of the keyframe line.
- Click the keyframe box (☑).

Note: You cannot remove the beginning and ending keyframes for any effect.

To remove all but the first and last effect keyframes for an effect:

- 1 In the Timeline window, select the clip to which the effect is applied.
- 2 In the Effect Controls palette, click the stopwatch icon (⌛) in the Effect Enabled button next to the effect name.

To reposition a keyframe:

Drag the keyframe to a new position on the keyframe timeline.

Note: You can drag the first and last keyframes to reset the time the effect begins or ends. A black keyframe line appears when you drag either of these two keyframes, indicating that no effect will be applied in that area. You can reposition keyframes only for effects with adjustable controls. To make it easier to drag the default keyframes, deselect the clip by clicking in an empty area in the Timeline.

Using After Effects effects

Premiere 6.0 includes many Adobe After Effects effects. You can distinguish After Effects effects from Premiere effects by the After Effects icon (Ⓐ). Some After Effects effects replace existing Premiere 5.0 effects, while others are new to Premiere. Replaced effects can be found in the Obsolete folder in the Video effects palette. For more information on working with your older projects that include obsolete effects, see “Obsolete effects” on page 332.

Note: Only those After Effects effects that are installed with Premiere 6.0 are supported.

Using effects from other products

In addition to the dozens of effects included with Premiere, many effects are available in the form of plug-ins, which you can purchase from third-party vendors or acquire from other compatible applications. For example, many Adobe Photoshop plug-ins can be copied into the Premiere Plug-ins folder to use in your video work.

An effect is available to Premiere when its plug-in software file is present in the Plug-ins folder, which is stored in the Adobe Premiere 6.0 folder by default. If you purchased additional plug-in effects, purchased Premiere as part of a hardware package, or removed effect files from the Plug-Ins folder, you may have a different set of effects than those described in online Help.

Obsolete effects

Many of Premiere’s video effects have been replaced by After Effects video effects. One Premiere 5.x audio effect is also obsolete. If you are working on a Premiere 5.x or earlier project that uses an obsolete (replaced) effect, you can continue to use it in Premiere 6.0 (settings you used for the obsolete effects remain intact). However, if you are creating a new Premiere 6.0 project, use the newer effects because the obsolete ones are intended only for Premiere 5.x project compatibility. All obsolete video effects reside in the Obsolete folder of the Video Effects palette. The obsolete audio effect resides in the Obsolete folder of the Audio Effects palette.

To access Obsolete effects:

- 1** Choose Window > Show Video Effects or Window > Show Audio Effects.
- 2** If the Obsolete folder is not visible in the list, choose Show Hidden from the Video Effects or Audio Effects palette menu.
- 3** Expand the Obsolete folder to see the effects.

http://



10



Chapter 10: Producing Final Video

When you have finished assembling and editing clips in the Timeline, you can generate the final video. The options you choose when producing the final video depend on how it will be used. Use the information in this chapter to produce videos in the following ways:

- Record the Timeline directly to videotape as it plays from your computer.
- Export a video file for viewing over the World Wide Web.
- Export an AVI or QuickTime video file for viewing from a hard disk, removable cartridge, or CD-ROM. Through plug-in software modules, Premiere can also export formats provided by other software manufacturers or by software included with video-capture cards.

To create motion-picture film from a Premiere project, you must have the proper hardware for video or film transfer or have access to a service provider that offers the appropriate equipment and services.

About exporting video from Premiere

The program you've edited in the Timeline is not available as an independent video file until you export it. After export, you can play it in other video playback or editing programs and move it to other disks or platforms. Before export, make sure that the Timeline is ready to output at the quality you require. For example, replace any offline files with high-resolution files suitable for final export. You can also export from the Source or Program views or the Storyboard or Clip windows, and you can specify a range of frames to export.

File types available for export

You can export a video program directly to videotape, or to a variety of video, audio, or still-image file formats. In addition to Premiere's Movie Export options (File > Export Timeline > Movie, or File > Export Clip > Movie), you can use any of the following plug-in options: Save for Web, Advanced Windows Media (Windows only), or Advanced

RealMedia Export. For detailed information on these plug-ins, see the plug-in's online Help, or visit the plug-in manufacturer's Web site. The following file formats are available when you export. Additional file formats may be available in Premiere if provided with your video-capture card or if you have added separately available plug-in software.

Video formats Microsoft AVI, Animated GIF, QuickTime, MPEG, RealMedia, Windows Media

Audio-only formats AIFF, MP3, and Windows Audio Waveform (Windows only)

Still-image and sequence formats Filmstrip, FLC/FLI (Windows only), GIF sequence, PICT and PICT sequence (Mac OS only), Targa and Targa sequence, TIFF and TIFF sequence, Windows Bitmap and Windows Bitmap sequence (Windows only)

Note: Notations such as “Windows only” or “Mac OS only” refer to features that are specific to the Windows or Mac OS versions of Premiere. They are not intended to indicate whether a given file format can be opened or played on a particular computer platform.

Exporting to videotape

You can record your edited program onto videotape directly from your computer. This can be as simple as playing the Timeline and recording on a connected DV camcorder or analog VCR. You can also use Premiere to control a deck or camera if your computer is properly connected to a deck or camera that supports device control. Use the Print to Video or Export to Tape commands to play video on a black background for recording on videotape. Print to Video can also zoom frames, so that quarter-screen video plays at full-screen size.

When recording directly from the Timeline, Premiere uses settings from the Project Settings dialog box. Many video-capture cards include Premiere-compatible plug-in software that provides a menu command for recording to videotape. Consequently, if the options you see are different than those described here, refer to your capture card or plug-in documentation for instructions on the most efficient way to export to tape.

If you will play the video program from the Timeline while recording directly to videotape, make sure that the project is using compression settings that preserve the highest picture quality without dropping any frames. Tune the settings for the computer on which you will play the program during videotape recording.

When you record DV video back to DV tape, all that is required is the IEEE 1394 connection. However, if you plan to record DV audio and video to an analog format, you'll need a device that is capable of converting DV audio and video to analog using the connectors supported by your analog video recorder. Most DV cameras and all DV video tape recorders are capable of this conversion; some DV cameras require you to record the video to DV tape, and then dub the DV tape to the analog video recorder.

 *To give your recording deck a few seconds or more of additional time before your video program starts and after it ends, add a black or color matte before and after the program in the Timeline. In addition, if you plan to have a postproduction facility duplicate your videotapes, add a minimum of 30 seconds of color bars and tone at the beginning of your program to aid in video and audio calibration. See “Creating color bars and a 1-kHz tone” on page 226.*

To prepare a DV program for videotape recording:

- 1 Connect the DV device (camcorder or deck) to your computer using an IEEE 1394 connection. The small 4-pin connector attaches to the DV device, and the large 6-pin connector attaches to the computer. The connection point on your DV device may be marked DV IN/OUT or IEEE 1394.
- 2 Turn the DV camcorder on and set it to VTR mode.
- 3 Start Premiere and open your project.
- 4 Choose Project > Project Settings > General. Click Playback Settings.

Note: *When you select a DV preset, the Editing Mode automatically is set to DV Playback (Windows) or QuickTime (Mac OS), both of which provide additional DV playback settings.*

- 5 If Editing Mode is set to DV Playback, select the following settings and then click OK:
 - Select Playback on DV Camcorder/VCR. This option plays back all DV-compressed clips to your video (NTSC/PAL) monitor or the LDC screen on your camcorder.
 - If you want to see your DV-compressed clips on the desktop as well as the output device, select Playback on Desktop. To save CPU cycles by not simultaneously outputting to two devices, do not select this option.
 - Select Render Scrub Output to DV Camcorder/VCR to see the results of render-scrubbing on your output device.
 - Select Play Audio on Desktop while Scrubbing to hear the audio on your desktop instead of the output device.

- 6 If Editing Mode is set to QuickTime, select the following settings and then click OK:
- For Output Device, select FireWire to play back all DV-compressed clips to your video (NTSC/PAL) monitor.
 - For Output Mode, select the appropriate NTSC or PAL mode. The Frame Size and Frame Rate for the selected mode automatically appear below.
 - Select Play Audio on the Output Device Only to play audio through the selected output device. When FireWire is selected, audio plays through the FireWire device (if Desktop is selected, audio plays to the desktop). If you don't select this option, audio *always* plays to the desktop.

Note: Audio and video may not be synchronized if played back through different devices.

- For Sample Rate, select the sample rate used by your DV camera. If you chose the correct preset when you started the project, this should already be set correctly. Most DV cameras use a sample rate of 32 kHz or 48 kHz; however 44.1 kHz is an available option for some cameras, so if your camera uses 44.1 kHz, you can select that here. See your DV camera's documentation for supported audio settings.

Note: Always capture and edit using the same audio sample rates that your DV camera supports. Do not mix audio sample rates on the same tape or in the same project.

- If you want to see DV-compressed clips on the selected output device and the desktop, select Play Also on Desktop When Playing to the Output Device. To save CPU cycles by not simultaneously outputting to two devices, do not select this option.

Note: When this option is not selected, scrubbing playback still appears on both the desktop and the NTSC/PAL video monitor.

- If high-quality playback is required, select High-Quality Playback and High-Quality Scrubbing. Otherwise, do not select this option. When this option is deselected, video plays back and scrubs faster because there is less impact on the CPU.
- Select Deinterlace Desktop Playback to deinterlace video before displaying it in the Clip or Monitor window. Deinterlaced video appears less blurry at the edges of moving objects. This option has no effect on output or previews to an external device.
- Select Show Marker Comments if you've added marker comments to the project and want them to display on your selected output device. See "Using Timeline markers for comments" on page 187.

- 7 Click OK to close the Project Settings dialog box.
- 8 Choose Edit > Preferences > Scratch Disks and Device Control.
- 9 Specify the scratch disk for captured movies. See “Setting up Premiere’s scratch disks” on page 88.
Note: The length of a captured clip may be limited by the file-size limits of your operating system; see “File-size limitations” on page 116.
- 10 Select DV Device Control 2.0 (or later) for Device and click Options. If necessary, select your camera brand and model.
- 11 Select the appropriate timecode format for your device and click OK.
- 12 Click OK to close the Preferences dialog box.

To record the Timeline on videotape using DV device control:

- 1 Make sure that your video recording device is on and that the correct (prestriped with timecode) tape is in the device. Locate and note the timecode for the location at which you want to begin recording.
- 2 Choose File > Export Timeline > Export to Tape.
Note: The Export to Tape command is available only if you have a supported DV device and use the DV Device Control plug-in.
- 3 Select Activate Recording Deck to let Premiere control your deck.
- 4 Select Assemble at Timecode and type the In point on the tape where you want recording to begin. If you don’t select this option, recording begins at the current tape location.
- 5 For Movie Start Delay, type the number of quarter-frames that you want to delay the movie so that you can synchronize it with the DV device recording start time. Some devices need a delay between the time they receive the record command and the time the movie starts playing from the computer.
- 6 For Preroll, type the number of frames that you want Premiere to back up on the recording deck before the specified timecode. Specify enough frames for the deck to reach a constant tape speed. For many decks, 5 seconds or 150 frames is sufficient.
- 7 Click OK.

To record the Timeline on videotape using analog video device control:

- 1 Make sure that your video recording device is on and that the correct tape is in the device.
- 2 Choose Edit > Preferences > Scratch Disks/Device Control and select your device control plug-in from the Device menu. If available, click Options and set your options as necessary; then click OK.
- 3 Choose File > Export Timeline > Export to Tape and specify options as necessary.

Note: Device control options vary depending on the device-control plug-in you use. See the documentation that came with the device-control plug-in.

To record the Timeline on videotape without device control:

- 1 In the Timeline, drag the work area bar over the portion of the video program that you want to record and press Enter (Windows) or Return (Mac OS) to build a preview file.
- 2 Make sure that the video program preview plays to your deck or camera. If it does not, review the steps for preparing a DV program for videotape recording, or see the documentation for your analog device.
- 3 Make sure that your video recording device is on and that the tape is cued to the point where you want to start recording.
- 4 Position the edit line at the beginning of the Timeline (or work area).
- 5 Press the Record button on your device.
- 6 Press the Play button in the Program view of the Monitor window.

To record the Timeline using Print to Video:

- 1 In the Timeline, drag the work area bar over the portion of the video program that you want to record and press Enter (Windows) or Return (Mac OS) to build a preview file.
- 2 Make sure that the video program preview plays to your deck or camera. If it does not, review the steps for preparing a DV program for videotape recording, or see the documentation for your analog device.
- 3 Make sure that your video recording device is on and that the tape is cued to the point where you want to start recording.

- 4 Choose File > Export Timeline > Print to Video. Specify options (see “Playing back full-screen video” on page 234). For the Play Black for _ Seconds option, make sure that you type a long enough time for the speed of the video recording device to stabilize before the video starts.
- 5 Click OK, and start the video recording device.

About creating Internet media

In general, Internet video is constrained by delivery data rates that are even lower than those used for CD-ROM playback. If you use Premiere’s Movie Export option to export your video program for the Web, use the guidelines for CD-ROM exporting (see “About creating a video file for CD-ROM playback” on page 345), but tune them to the data rates available on the networks through which you expect to deliver the video. If you use one of the Web-optimized plug-in options, such as Save for Web export, choose a delivery option (such as 28K modem, 56K modem, ISDN, or Broadband/LAN) that best represents the viewing capabilities of your audience.

You have many choices for delivering video over the Internet. Each method has specific capabilities and workflow requirements, so consider the choices carefully.

Streaming video

Streaming video resembles conventional television in that video is sent to you frame by frame, without downloading a large file to your hard drive. Streaming video on the Web is constrained by the limited bandwidth (56 Kbps or less) of most consumer modems. However, streaming video can be deployed effectively within intranets where high-speed bandwidth is more readily available.

The following streaming video formats are available for export from Premiere: QuickTime Streaming, Windows Media, RealVideo, and RealG2Streaming. You can create streaming video using any of the built-in Web export options: Save for Web, Advanced RealMedia Export, or Advanced Windows Media Export (Windows only).

Progressive downloadable video

A progressive download movie (also called a *hinted* movie) can begin playing before it is completely downloaded. The movie player (for example, QuickTime, MediaPlayer, or RealPlayer) begins playback when it calculates that the movie will be fully downloaded by the time playback reaches the end of the video.

The following downloadable video formats are available for export from Premiere: QuickTime Progressive Download, Windows Media, RealVideo, and RealG2 Web Download. You can create progressive download video using any of the Web export plug-ins: Save for Web, Advanced RealMedia Export, or Advanced Windows Media Export (Windows only).

MPEG video

Motion Picture Experts Group (MPEG) is a file format that compresses video files effectively but is not as standardized as QuickTime or AVI. There are actually several variations of MPEG. The version generally used for Internet and CD-ROM is MPEG-1, which provides picture quality nearly comparable to VHS. MPEG-2 can provide SVHS picture quality. However, the keyframe-based compression and variable bit rate that make MPEG popular for delivery of final video require significant processing time.

You can create MPEG video using the Save for Web export option.

MP3 audio

Motion Picture Experts Group (MPEG) 1 Layer 3 is a file format that compresses audio files at a 1:24 to 1:5 ratio. The high compression rate makes MP3 files smaller and of higher quality than most other audio formats.

You can create MP3 audio files using the Save for Web export option.

Animated GIF

Animated GIF is best suited for solid-color motion graphics at a small frame size, such as an animated company logo. It works better for synthetic graphics than for live-action video. It is convenient because it is viewable in most Web browsers without requiring a plug-in, but you cannot include audio in an animated GIF file. Export animated GIF the same way you do any other file, making sure that you choose Animated GIF as the File Type. See “Exporting a video” on page 346. For best results, test completed Animated GIF files in a Web browser before distributing.

About creating a video file for CD-ROM playback

When you create a video file to be played from a CD, you may need to specify export settings that take into account the wide range of hardware that your audience might be using, possibly including older single- or double-speed CD-ROM drives.

If your audience does use older CD-ROM drives, it becomes important to tune your exported video file for a low data rate. You can limit the data rate of your program simply by specifying it in Premiere, but if the video file still does not play well on your audience's computers, you may also want to make the following adjustments:

- Lower the data rate and quality as far as you can without losing too much picture quality, if you specified a codec that lets you adjust data rate and quality. See “About data rate” on page 353 and “Exporting a video” on page 346.
- Lower the frame rate as far as you can without making motion seem too jerky. Start at 15 frames per second. See “Exporting a video” on page 346.
- Lower the color depth to 256 colors. In addition to lowering the data rate, this may improve picture quality of video on a system or in presentation software that can display only 256 colors (8-bit color). See “Exporting a video” on page 346.
- Crop the picture for optimum viewing at a small size, reduce video noise to enhance compression, or adjust gamma for the target monitor, using the Special Processing panel in the Export Settings dialog box. See “Exporting a video” on page 346.
- Choose a file type and codec appropriate for the target audience. For example, for a cross-platform CD-ROM, you might specify a QuickTime codec. Choose a codec designed for low data rates, such as Indeo, Cinepak, or Sorenson Video.
- Choose File > Export Timeline > Save for Web, and select the AVI CD-ROM or QuickTime CD-ROM setting. Both of these settings automatically compress and save the file with the optimal settings for playback from a CD.

About creating a video file for use in other software

Premiere exports to many formats that are readable by other applications. For example, you can export a QuickTime movie for use in Adobe After Effects. When preparing to export to a video file for use in other video-editing or special-effects software, answer the following questions:

- What file formats and compression methods does the other software import? This helps determine which format you will use to export.
- Will you be transferring across computer platforms? This may constrain the choice of file formats and compression methods further. Consider using high-quality cross-platform codecs (transcoders) such as QuickTime Motion JPEG A or B, or the Animation codec.
- Will you be superimposing the Premiere clips over other clips? If so, preserve alpha channel transparency when exporting from Premiere.
- What is the highest quality compression method that the other software imports? Using high-quality compression limits the degree of compression that can be applied to the video file while retaining quality. You want to retain the highest possible level of picture quality until the editing process is complete. For maximum quality, choose the None compressor (no compression) if you have sufficient disk space to store the very large file that will result.
- Do you want to paint on frames? If so, you can export to Filmstrip format and edit in Adobe Photoshop (see “Exporting a filmstrip file for editing in Adobe Photoshop” on page 349). Alternatively, you can export frames as a numbered sequence of individual still-image files, and edit each file in Photoshop.
- Do you want to use a single frame as a still image? If so, see “Exporting a filmstrip file for editing in Adobe Photoshop” on page 349.

Exporting a video

You can prepare variations of one program or clip for several uses. For example, you can prepare low- and high-resolution versions of a program or clip, or create separate versions for broadcast television, CD distribution, and Web viewing. You can also automate the export of project variations using batch processing. See “Processing a batch of projects” on page 351.

To export a video using a Web or CD-ROM optimized plug-in:

- 1 Activate the Timeline, Source view, Program view, or a Clip window. If you are exporting the Timeline and it includes virtual clips, make sure that the work area in the Timeline includes the main video program only. See “Nesting edits using virtual clips” on page 222.
- 2 Choose File > Export Timeline (or Export Clip) > Save for Web, Advanced RealMedia Export, or Advanced Windows Media (Windows only).

3 Select your settings and click OK or Start. See the plug-in's online Help or PDF documentation for details.

To export a video using Premiere's export:

- 1** Activate the Timeline, Source view, Program view, or a Clip window. If you are exporting the Timeline and it includes virtual clips, make sure that the work area in the Timeline includes the main video program only. See "Nesting edits using virtual clips" on page 222.
- 2** Choose File > Export Timeline (or Export Clip) > Movie.
- 3** Click Settings and choose your settings as necessary. See "Choosing export settings" on page 355.
- 4** Click OK to close the Settings dialog box.
- 5** Specify a location and filename, and click OK. If you want to cancel exporting, press Esc; it may take several seconds to complete the cancellation.

 *Use the Save and Load buttons in the Export Movie Settings dialog box to save and later quickly load export settings that you use frequently. Loading saved settings is particularly useful when you create several types of video files (for example, NTSC and Web video) from the same project.*

Exporting a still image

You can export any frame or still-image clip to a still-image file. The frame is exported from the current time position in the Timeline, Clip window, Source view, or Program view.

To export a still image:

- 1** Choose File > Export Timeline > Frame.
- 2** Click Settings.
- 3** Choose a File Type. Click Advanced Settings for the file type you chose (if available), specify options, and click OK. For the Advanced Settings available for GIF, see "Animated GIF" on page 344.
- 4** Click Next. In the Video Settings panel, specify the Frame Size and color Depth (see "Exporting a video" on page 346).

- 5 Click Next. In the Keyframe and Rendering Options panel, specify options as needed.
- 6 Click Next. In the Special Processing panel, click Modify, and specify options as needed.
- 7 Click OK to close the Export Still Frame Settings dialog box.
- 8 Specify a location and filename, and then click OK.

Exporting a sequence of still images

You can export a clip or program as a sequence of still images, with each frame in a separate still-image file. This can be useful to move a clip to animation and three-dimensional applications that do not import video file formats, or for use in animation programs that require a still-image sequence. When you export a still-image sequence, Premiere numbers the files automatically.

To export a series of still images:

- 1 Choose File > Export Timeline > Movie.
- 2 Click Settings.
- 3 For File Type, choose a still-image sequence format (generally any file type ending in the word “sequence” and the FLC/FLI (Windows only) file type).
- 4 Choose the frames to export from the Range menu.
- 5 Make sure that Export Video is selected.
- 6 Click Next and confirm video settings (see “Exporting a video” on page 346).
- 7 Click Next. In the Keyframe and Rendering Options panel, specify options as needed, and then click OK.
- 8 Specify a location where you want to export all of the still-image files. It’s usually best to specify an empty folder set aside so that the sequence files don’t become mixed with other files.
- 9 If you want, type a numbered filename. To specify the number of digits in the filename, determine how many digits will be required to number the frames, and then add any additional zeroes you want. For example, if you want to export 20 frames and you want the filename to have five digits, type Car000 for the first filename (the remaining files will automatically be named Car00001, Car00002, ..., Car00020).
- 10 Click OK to export the still-image sequence.

Exporting a filmstrip file for editing in Adobe Photoshop

When you want to edit a clip in Adobe Photoshop, you can use the Filmstrip format, which was specifically created for this purpose. The Filmstrip format is useful when you want to paint directly on video frames, a process known as *rotoscoping*. You can export a video clip or a section of the Timeline as a *filmstrip*.

A filmstrip is a single file that contains all the frames of the clip. If your computer doesn't have enough memory to enable Photoshop to load the filmstrip file, consider exporting the clip as numbered still images instead so you can edit each frame as a separate file (see "Exporting a sequence of still images" on page 348). A filmstrip opens in Photoshop as a series of frames in a column, with each frame labeled by number, reel name, and timecode. If the column created by the filmstrip frames is more than 30,000 pixels tall, the frames continue in a second column. This size limitation is the maximum image dimension that Photoshop can handle. The number of frames displayed depends on the duration of the clip and the frame rate selected when the filmstrip was exported from Premiere.

When editing a filmstrip in Photoshop, use the following guidelines for best results:

- You can paint on the gray lines dividing the frames of the filmstrip. It won't hurt the file, but Premiere will display only the part of each frame that lies within the frame border.
- You can edit the red, green, blue, and alpha channels in the filmstrip file. However, use only channel 4 as the alpha channel; other alpha channels are not recognized.
- Do not resize or crop the filmstrip.



If you simply want to export a single frame, you don't need to use the Filmstrip format. Instead, export a single still frame. See "Exporting a still image" on page 347.

To export a clip as a filmstrip:

- 1 Choose File > Export Timeline (or Export Clip) > Movie.
- 2 Click Settings.
- 3 For File Type, choose Filmstrip, and choose the frames to export from the Range menu.
- 4 Make sure that Export Video is selected.

5 Click Next, and confirm video settings (see “Exporting a video” on page 346). Make sure that the frame rate is the same as the project frame rate. Then click OK.

Note: If the video contains interlaced fields, select Keyframe and Rendering Options from the menu at the top of the dialog box; for Field Settings, select Upper Field First if the original source video is field-1 dominant, or Lower Field First if the original video is field-2 dominant. If you don’t know the field dominance of the original video, ask the creator of the original video or refer to the documentation for the hardware used to create it.

6 Specify a location and filename, and then click Save.

After editing the filmstrip and saving it in Filmstrip format from Photoshop, use it as a clip in a Premiere project by importing it as you would any other compatible file. See “Importing clips” on page 151.

Exporting a project for use in Adobe After Effects

You can import a saved Premiere project file into Adobe After Effects and apply finishing touches such as advanced keying features, effects, and animations. After Effects preserves the order of clips in the Timeline, footage duration, and marker and transition locations. After Effects converts transitions and titles in your project to solid layers, maintaining their original location and duration. It discards all Premiere transparency, motion, and effect settings.

After Effects provides many of the same export features as Premiere, so when you are done working, you can render your project in After Effects using any of the supported file formats. For more information, see the After Effects documentation.

To open a Premiere project in After Effects:

- 1 Save and close your project in Premiere.
- 2 Open After Effects and choose File > Import > Premiere as Comp.
- 3 Locate and select the Premiere project file, and click Open.

Processing a batch of projects

You can export multiple video programs or clips to multiple files automatically. The Batch Processing command uses the export settings and compression options you specify for each video file being created. You can create and save multiple batch lists for easy, repeatable exporting of groups of projects. Batch processing can save time and greatly simplify the following tasks:

- Exporting several video files overnight
- Testing several different export settings files to find out which work best
- Creating versions for different media, such as videotape, CD, and Web delivery
- Creating versions for different editing tasks, such as offline editing or rotoscoping

To export a batch of files:

- 1 Choose Project > Utilities > Batch Processing.
- 2 Click Add. Select a project or video file that you want to add to the list, and click Open. Repeat for as many projects or video files as you want to export.
- 3 For each file in the list, do the following:
 - Select the project or clip, and click Target. Specify the location and filename of the file that will be produced from this project or clip, and click Save.
 - Click Settings if you want to verify the project settings for a selected project or clip.
- 4 Do one of the following:
 - To make sure project source files are ready for processing, select any number of projects in the list and click Check. This is particularly important if you plan to leave the computer unattended, because missing files will stop all processing. Premiere opens each selected project in turn and verifies that the clip files exist on disk that correspond to the clip instances used in each selected project. If a clip file is missing, Premiere notifies you in the same way it does when you open a project. See “Opening a project” on page 85.
 - To process the entire batch list, click Make, select Make All Sources in List, and click OK.
 - To process a continuous range of projects in the list, click to select the first project you want to process, hold down Shift as you click the last project you want to process, click Make, select Make Selected Sources Only, and click OK.

- To process a discontinuous range of projects in the list, click to select the first project you want to process, hold down Control (Windows) or Command (Mac OS) as you click each additional project you want to process, click Make, select Make Selected Projects Only, and click OK.

Warning: *If you click Cancel, you will lose all of your changes since you opened the Batch Processing dialog box. If you decide not to make a movie but want to retain batch list settings you specified, save your settings as described in the following procedures. At a later time, you can open the Batch Processing dialog box and load those settings.*

To save, load, or delete an item from the Batch Processing list:

When the Batch Processing window is open, do any of the following:

- To delete a project or clip from the Batch Processing list, select a project or clip in the list, and click Delete.
- To save the Batch Processing list to disk, click Save, specify a location and filename, and click Save.
- To load a Batch Processing list from disk, click Load, locate and select a batch-processing list file, and click Open.

About export settings

When you export from Premiere, the way you adjust settings for export depends on the kind of output you want:

- When recording directly from the Timeline (File > Export Timeline > Print to Video or Export to Tape), Premiere uses settings from the Project Settings dialog box.
- When exporting to a movie (File > Export Timeline > Movie), Premiere uses settings in the Export Settings dialog boxes.
- When exporting to a Web plug-in (File > Export Timeline > Save for Web, Advanced Windows Media, or Advanced RealMedia Export), the plug-in uses settings from the Project Settings dialog box and the plug-in dialog boxes. Refer to the plug-in's documentation for details.

Note: *Your capture card may include software that provides unique dialog boxes and options for export. If the options you see are not the same as those described in this chapter, refer to your capture card's documentation for information.*

To see a list of the capture, clip, project, and export settings currently used by your project, open the Settings Viewer window by choosing Project > Settings Viewer. For more information, see “Comparing settings using the Settings Viewer” on page 82.

About compression

When exporting a video program, you choose a compressor/decompressor, or *codec*, to compress the information for storage and transfer (such as on a CD) and to decompress the information so it can be viewed again. Compressing the video program makes it play smoothly on a computer. A wide range of codecs is available; no single codec is the best for all situations. For example, the best codec for compressing cartoon animation is generally not efficient for compressing live-action video.

The codec you use must be available to your entire audience. For instance, if you use a codec available only with a specific capture card, your audience must have the same capture card installed. Some formats, such as some DV and streaming-video systems, use dedicated codecs.

About data rate

With some video codecs, you can specify the *data rate*, which controls the amount of video information that must be processed each second during playback. Specifying a data rate in Premiere sets the *maximum* data rate, because the actual data rate varies depending on the visual content of each frame.

The data rate you specify depends on the purpose of the video. The following list describes data rate guidelines for some uses:

Videotape production The data rate should fall within the capabilities of the computer and hard disk that will play the Timeline or clip during videotape recording.

Hard-disk playback If your final video will be played back from a hard disk, determine the typical data transfer rate of your audience’s hard disks and set the data rate accordingly. If you are exporting video to be used in another editing system, or to be imported into a compositing application such as Adobe After Effects, you’ll want to export at the maximum quality. Use a lossless codec or the codec supported by your video capture card, and specify the data rate that the editing system supports for video capture and editing.

CD-ROM playback The data rate for video played from a CD-ROM depends on the speed of the CD-ROM drive. For example, if you are preparing a final video file for a double-speed CD-ROM drive (300K per second) you might specify between 150 to 200K per second to account for both the data rate of the drive and for the system overhead required to move the data.

Intranet playback The data rate can be 100K per second or faster, depending on the speed of your *intranet*. An intranet is an in-house or private network that uses Internet network protocols. Because they are limited in scope, intranets generally use higher-quality communications lines than standard telephone lines, so they are usually much faster than the Internet.

Streaming video over the World Wide Web The data rate should account for real-world performance at the target data rate. For example, the data rate for streaming video designed for a 28,800 bps (bits per second) connection is often set to 20,000 bps. That's because factors such as data volume and line quality often prevent telephone-based Internet connections from consistently achieving their stated data rate.

Downloading a video file over the World Wide Web The data rate is less important than the size of the video file on disk, because the main concern is how long it takes to download the file. However, it still may be desirable to reduce the data rate for downloaded video because doing so reduces the size of the video file, making it download faster.



Use the Get Properties For command to analyze the data rate of files you export. See “Analyzing clip properties and data rate” on page 157.

About compression keyframes

Compression keyframes are different from the keyframes placed in the Premiere Timeline window. Compression keyframes are automatically placed during export at regular intervals in the movie. During compression, they are stored as complete frames. The frames between the keyframes, called intermediate frames, are compared to the previous frame and only the changed data is stored. This process can greatly reduce file size, depending on the spacing of the keyframes. Fewer keyframes and more intermediate frames result in smaller file sizes, but produce lower-quality images and playback. More keyframes and fewer intermediate frames result in significantly larger file sizes, but produce higher-quality images and playback.

Choosing compression settings is a balancing act that varies depending on the type of video material, the target delivery format, and the intended audience. Often, the optimal compression setting is arrived at through trial and error.

Choosing export settings

As part of the process of exporting, check the options in the Export Settings dialog box. The initial export settings are the same as the settings you specified in the Project Settings dialog box when you first started the project. Export settings don't update as you work on your project, however, so it's a good idea to make sure that all export settings are still the ones you want. Although the Export Settings dialog box is similar to the Project Settings dialog box, important differences exist. For example, the Special Processing panel is included so that you can apply certain changes to all clips in the Timeline at export time, such as resizing, cropping, and noise reduction.

***Note:** Some capture-card software and plug-in software provide their own dialog boxes with specific options. If the options you see are different than those described in this User Guide refer to the documentation for your capture card or plug-in.*

General export settings

The following options are available in the General panel of the Export Settings dialog box:

File Type Select the kind of file you want to export.

Advanced Settings Click if available. These options vary depending on the file type you choose. The following advanced settings options are available for Animated GIF or GIF Sequences:

- **Dithering:** Select to simulate colors that are not available in the Web-safe color palette used by Web browsers. Dithering simulates unavailable colors using patterns that interperse pixels from available colors. Dithered colors may look coarse and grainy, but dithering generally improves the apparent color range and the appearance of gradations. Deselect this option to move unavailable colors to the next closest color in the palette; this may cause abrupt color transitions.
- **Transparency:** Select None from the menu to create the movie in an opaque rectangle. Select Hard to convert one color into a transparent area; click Color to specify the color. Select Soft to convert one color into a transparent area and soften the edges; click Color to specify the color.

- **Looping:** Select if you want the animated GIF to play continuously without stopping. Deselect this option if you want the animated GIF to play only once and then stop. This option is not available for a GIF sequence.

Range Select the range of time to export. If the Timeline or the Program view is active, you can select Work Area to export the frame range marked by the work area markers (see “Previewing a video program” on page 227). If you are exporting from the Source view or a Clip window, and In and Out points are marked, you can select In to Out to export the marked range only.

Export Video Select to export the video tracks, or deselect to prevent exporting video tracks.

Export Audio Select to export the audio tracks, or deselect to prevent exporting audio tracks.

Open When Finished Select if you want the exported file to be opened in Premiere after exporting is complete.

Beep When Finished Select if you want Premiere to sound an alert when exporting is complete.

Embedding Options Select Project Link from this menu if you want the exported file to include information necessary to use the Edit Original command. When a file contains this information, you can open and edit the original project from within another Premiere project or from another application that supports the command. Select None from this menu if you do not want to include the information.

Video export settings

The following options are available in the Video Settings panel of the Export Settings dialog box:

Compressor Choose the codec (compressor/decompressor) for Premiere to apply when exporting a file, and click Configure (if available) to set options specific to the selected codec. The codecs available depend on the File Type you chose in the Export Settings panel.

***Note:** If you cannot find options that your codec provides, see the documentation provided by the hardware manufacturer. Some codecs included with video-capture hardware require that you set compression options in dialog boxes provided by the codec, instead of through the options described in this book.*

Depth Choose the *color depth*, or the number of colors to include in video that you export. This menu may not be available if the selected Compressor supports only one color depth. You can also specify an 8-bit (256-color) palette when preparing a video program for 8-bit color playback—for example, to match the colors on a Web page or in a presentation. When available, click Palette and then either select Make Palette from Movie to derive a color palette from the frames used in the video program, or select Load Palette Now to import a color palette that you prepared and saved previously. You can load color palettes in the .ACO (Photoshop color swatch), .ACT (Photoshop color palette), or .PAL (Windows palette—Windows only) format.

Note: *With the QuickTime file type, you can attach a 256-color palette to a movie of any bit depth. You can specify a palette for 24-bit movies to use when displaying on 8-bit monitors, and you can prevent palette “flashing” by attaching the same palette to many movies. Video for Windows supports attaching a palette only to an 8-bit movie.*

Frame Size Specify the dimensions, in pixels, for video frames you export. Select 4:3 Aspect to constrain the frame size to the 4:3 aspect ratio used by conventional television. Some codecs support specific frame sizes. Increasing the frame size displays more detail but uses more disk space and requires more processing during playback.

Frame Rate Choose the number of frames per second for video you export. Some codecs support a specific set of frame rates. Increasing the frame rate may produce smoother motion (depending on the original frame rates of the source clips) but uses more disk space.

Quality Drag the slider or type a value to affect the picture quality of and disk space used by exported video. If you are using same codec to capture and export, and you’ve rendered previews of the Timeline, you can save rendering time by matching the export quality setting with your original capture quality setting. For example, if you captured clips at 50% quality, set the export quality to 50% also. Premiere then performs a straight file copy of the data whenever possible, instead of recompressing the data frame by frame. Increasing quality above the original capture quality does not increase quality, but may result in longer rendering times.

Limit Data Rate to _ K/Sec Select (if available for the selected compressor) and type a data rate to place an upper limit on the amount of video data produced by the exported video when it is played back.

Note: *In some codecs, quality and data rate are interrelated, so that adjusting one option automatically alters the other.*

Recompress Select to ensure that Premiere exports a video file that is under the data rate you specified. Choose Always from the Recompress menu to compress every frame even if it is already within the data rate, or choose Maintain Data Rate to preserve quality by compressing only the frames that are above the specified data rate. Recompressing previously compressed frames may lower picture quality. Deselect Recompress to prevent current compression settings from being applied to clips that were not altered when you edited them into the program.

Audio export settings

When you choose Audio Settings from the menu at the top of the Export Movie Settings dialog box, you can specify the following options:

Rate Choose a higher rate for better audio quality in an exported file, or choose a lower rate to reduce processing time and disk-space requirements. CD quality is 44.1 kHz. Resampling, or setting a different rate than the original audio, also requires additional processing time; avoid resampling by capturing audio at the final rate.

Format Choose a higher bit depth and stereo for better quality, or choose a lower bit depth and mono to reduce processing time and disk-space requirements. CD quality is 16-bit stereo. Stereo provides two channels of audio; Mono provides one channel.

Compressor Specify the codec for Premiere to apply when compressing audio. The codecs available depend on the File Type you specified in the General panel in the Export Settings dialog box. Some file types and capture cards support only uncompressed audio, which has the highest quality, but uses more disk space. Check with your capture card's documentation before choosing an audio codec.

Interleave Specify how often audio information is inserted among the video frames in the exported file. See your capture-card documentation for the recommended setting. A value of 1 frame means that when a frame is played back, the audio for the duration of that frame is loaded into RAM so that it can play until the next frame appears. If the audio breaks up when playing, the interleave value may be causing the computer to process audio more frequently than it can handle. Increasing the value lets Premiere store longer audio segments that need to be processed less often, but higher interleave values require more RAM. Most current hard disks operate best with 1/2- to 1-second interleaves.

Enhanced Rate Conversion Specify a level of quality for converting the sample rates of clips in the Timeline to the sample rate you specified in the Rate option. Enhanced Rate Conversion controls both rate upsampling and downsampling. The Off option resamples audio most quickly but produces moderate quality. The Better option balances quality with processing time. The Best option resamples audio for the highest possible quality but requires the most processing time.

Logarithmic Audio Fades Select to process audio gain levels using the logarithmic scale used by the human ear and by conventional volume controls. Deselect this option to process gain changes using a linear curve. Selecting this option creates more natural-sounding changes as sounds become louder or softer, but may increase audio processing time. This option does not directly affect the audio faders in the Timeline—only the overall gain level.

Create audio preview files if there are: Type a new number in one or both of these boxes if you are experiencing poor playback performance due to more audio tracks or audio effects than your CPU can handle in real time. When you type a number below the actual number of audio tracks or effects used, Premiere renders audio preview files before playing back the video program. Rendering preview files requires extra rendering time, but improves playback performance.

Keyframe and Rendering export settings

When you choose Keyframe and Rendering options from the menu at the top of the Export Movie Settings dialog box, you can specify the following settings as needed:

Ignore Audio Effects Select to export audio without processing applied effects. This option can be useful for exporting a rough cut, but remember to deselect it for the final cut.

Ignore Video Effects Select to export video without processing applied effects. This option can be useful for exporting a rough cut, but remember to deselect it for the final cut.

Ignore Audio Rubber Bands Select to process a video program excluding changes made using the Volume or Pan rubberband controls in the Timeline. This option can be useful for exporting a rough cut, but remember to deselect it for the final cut.

Optimize Stills Select to use still images efficiently in exported video files. For example, if a still image has a duration of 2 seconds in a project set to 30 frames per second, Premiere will create one 2-second frame instead of 60 frames at 1/30 of a second each. Selecting this option can save disk space if you used still images. Deselect this option only if the exported video file exhibits playback problems when displaying the still images.

Frames Only at Markers Select when you want to render only the frames at which you have added a Timeline marker. This option does not affect compression keyframes.

Fields Choose an option if required for your final medium. No Fields is the default and is the equivalent of progressive scan, the correct setting for computer display and motion-picture film. Choose Upper Field First or Lower Field First when exporting video for an interlaced medium such as NTSC, PAL, or SECAM. The option you choose depends on the specific video hardware you use.

Keyframe Every _ Frames Select and type the number of frames after which the codec will create a keyframe when exporting video.

Add Keyframes at Markers Select to create keyframes only where markers exist on the Timeline. For this to work, markers must exist in the time ruler in the Timeline (see “Using markers” on page 185).

Add Keyframes at Edits Select to create a keyframe at the beginning of each clip in the Timeline.

Note: Some codecs do not provide control over keyframes. In such codecs, the above options will not be available.

Special Processing export settings

When you choose Special Processing from the menu at the top of the Export Movie Settings dialog box, you can click Modify and specify the following options as necessary:

Left, Right, Top, and Bottom Type margin dimensions in pixels or drag the handles on the cropping rectangle to crop the exported video. The Size readout indicates the pixel dimensions of the frame after cropping. If you specified Cinepak compression, make sure that the final dimensions are divisible by 4, because Cinepak works most efficiently with 4x4 pixel cells.

Scale to (frame size) Select if you cropped the video and want to enlarge the cropped frame to match the Frame Size you specified in the Video Settings panel. Deselect this option if you want the video to be exported at the cropped size.

Slider under the Preview Drag to preview how the current Special Processing options affect other frames.

Noise Reduction Select to increase compression efficiency by reducing variations in pixel values. From the Noise Reduction menu, select Blur for a subtle blur, Gaussian for a stronger blur, or Median for a blur that attempts to preserve sharpness at edges. This option does not apply noise reduction to audio.

Better Resize Select if you specified cropping or scaling in this dialog box and want Premiere to use its own high-quality resizing method. Deselect to let the codec you selected perform resizing; many codecs resize faster but at the expense of picture quality.

Deinterlace Select to remove the secondary field from interlaced video and interpolate the lines of the dominant field. Deselect this option to deinterlace using the methods built into Video for Windows or QuickTime, which are not as effective as the method Premiere uses.

Gamma Select to specify a value by dragging the slider. Gamma adjusts midtones while preserving the lightest and darkest parts of the picture. This option helps compensate for differences between video display characteristics of different platforms. A gamma value of 1.0 changes nothing; a value of 0.7 or 0.8 is recommended for cross-platform playback.

Reset Click if you want to revert to the settings that were in use before you opened the Special Processing dialog box.

About creating motion-picture film

If you are editing a project for viewing on motion-picture film, first export the Premiere video program to a video file using high-quality settings. After you create the file, use a motion-picture *film recorder*, a hardware device that prints individual frames to motion-picture film frames. This service is most likely to be available from a postproduction facility. Motion-picture film can display more detail than most video formats, so your project may require a larger frame size than it would for videotape. The exact resolution you should use depends on the film stock to which you will print. For best results, discuss the project with your postproduction facility before you begin.

An NTSC video frame is displayed using two alternating fields of scan lines in an interlaced format. A motion-picture frame appears all at once in a progressive display. When you create motion-picture film from clips that were originally digitized from interlaced video, be sure to set field options properly for each clip in the Timeline. This ensures that motion will play back properly. See “Exporting a video” on page 346.

Exporting an edit decision list

An *edit decision list* (EDL) is necessary when you use Premiere for offline editing and plan to complete editing of source videotape or motion-picture film in a postproduction studio. An EDL contains the names of original clips, the In and Out points of those clips as they are used in a video program, and other editing information (such as split edits), depending on the EDL format. See “Understanding offline and online editing” on page 111.

Premiere can export an EDL in formats compatible with various edit controllers, including CMX, Grass Valley, and Sony. A generic EDL format is also provided. Supported EDL formats exist as plug-ins stored in the Plug-ins folder inside the Premiere folder, so you can add support for a new EDL format in the future if a Premiere-compatible plug-in becomes available. Most EDLs are transported to and from postproduction facilities on 3.5-inch disks formatted for MS-DOS®. On Mac OS, MS-DOS disks can be read automatically, formatted, and saved to using the PC Exchange software included with Mac OS.

Exporting an EDL

When you create an EDL in Premiere, the editing decisions you make in the Timeline are recorded in the EDL in text format. You can export the editing decisions to any of the EDL formats, and view and print the EDL by opening it in Premiere or in any word processor. You can also export the EDL in a format that an editing system can read directly. If the clips in the Timeline do not have a timecode (either assigned at the time they were captured or entered using the Timecode command in the Clip menu), Premiere assumes a starting time of 00:00:00:00.

Work closely with your postproduction facility to achieve the best possible results. Premiere provides many special effects that are unavailable on most traditional editing systems (see “Transitions, special effects, and superimposed clips in the EDL” on page 365). Your postproduction editor can suggest alternate effects to use before assembling the final video file.


Note: *To avoid confusion when working with NTSC EDLs, use a timebase of 29.97 fps. If you set a timebase of 30 fps, Premiere counts video frames in true 1/30ths of a second. Because all NTSC video is 29.97 fps, the timecode displayed in the Source view or Clip window will not match exactly the actual timecode on the source tape. This is not an issue for PAL or SECAM video, which are counted in whole frames at 1/25th of a second.*

To export a generic EDL:

- 1 Choose File > Export > Generic EDL.
- 2 Specify a location and filename, and click Save.


To export a project to a specific EDL format:

- 1 Choose File > Export Timeline, and choose an EDL format from the bottom of the Export menu.



- 2 Specify the following options (which may vary by the type of EDL you choose):
 - Title for this EDL to display in the EDL header.
 - Start Timecode for the time at which you want recording to start on the recording reel.
 - Frame Rate to match the time-counting method used by the EDL. The default is non-drop-frame timecode; select the Drop Frame option if you want. This option does not alter the frame rate.
 - Audio Processing for sound options (see “Audio in the EDL” on page 368).
 - Level Notes to annotate edit information with more detailed information. None includes no additional notes. Audio Only includes notes about audio levels, Keys Only includes notes about superimposition keys, and Audio and Keys includes both.
 - Create B-Roll to make a separate list of source clips used in transitions or keys when they require clips from the same source reel. This list, called a *B-roll conform list*, is used by the postproduction facility to make an additional source reel of clips used in transitions or keys.
 - B-Roll in Separate File to list B-Roll edits in a separate EDL if you selected Create B-Roll.
- 3 Click Wipe Codes and type the wipe pattern codes used by your postproduction facility.

- 4 Specify the following options as necessary, and then click OK:
- Load to replace the existing wipe codes with those from a file on disk.
 - Save to export the existing wipe codes to a file on disk.
 - Defaults to restore the preset wipe codes installed with Premiere.




See “Transitions, special effects, and superimposed clips in the EDL” on page 365.

- 5 Click Audio Mapping and assign Premiere audio tracks to tracks in the EDL using the following options:

- Stereo Grouping if you plan to use pairs of EDL audio tracks for stereo audio.

- Track and Destination list to assign Premiere audio tracks to any of the EDL audio tracks. Click Off to keep a Premiere audio track out of the EDL. If you selected a Stereo Grouping option, the EDL tracks are available in the list in pairs, not individually.



A. Stereo grouping pairs B. Destination pairs

- 6 Click OK, specify a location and name for the EDL, and click Save. You will also be asked to specify a location and name for a B-roll if necessary. The exported EDL appears in a text window.

Note: If you export your EDL to the CMX or Grass Valley format, the file must eventually be transferred to a disk formatted for those systems. Utility software that formats disks for CMX and Grass Valley systems is available from various companies.

Transitions, special effects, and superimposed clips in the EDL

Premiere includes many transitions, effects, and superimposition options that are not available in many online editing systems. A standard EDL recognizes only the cut, the dissolve, and some wipe transitions. The EDL modules available in Premiere attempt to translate the edits from your project to the standard EDL format in a single event. For example, the Cross Dissolve transition in Premiere is interpreted as a Dissolve transition by the standard EDL. Although many of the Premiere transitions cannot be adequately described in the EDL, the name of the Premiere transition is listed in a comment line in the EDL.

Premiere's effects and motion settings are completely ignored in a standard EDL. Superimposed clips are described as *keys*. The only transition permitted under a key is a Cut; other transitions under keys are removed from the EDL.

Many Premiere transitions correspond closely to wipe patterns that can be produced by a video *switcher*, a device that handles transitions in a conventional edit bay. Transitions that do not correspond to wipe patterns are interpreted as cross-dissolves. The following list describes Premiere transitions as they are interpreted by each standard EDL transition:

EDL Box Wipe Iris Cross, Iris Diamond, Iris Point, Iris Shapes, Iris Square, Iris Star, Multi-spin, Spiral Boxes, Swirl, Tumble Away, Zoom, Zoom Boxes, and Zoom Trails

EDL Circle Wipe Clock Wipe, Iris Round, and Peel Back

EDL Cross Dissolve Additive Dissolve, Channel Map, Cross Dissolve, Cross Stretch, Cross Zoom, Curtain, Displace, Dither Dissolve, Fold Up, Funnel, Image Mask, Luminance Map, Non-Additive Dissolve, Paint Splatter, Random Blocks, Random Invert, Slash Slide, Texturize, and Three-D

EDL Cross Split Wipe Center Merge, Center Peel, and Center Split

EDL Diagonal Wipe Page Peel, Page Turn, and Radial Wipe

EDL Horizontal Wipe Checkerboard, Random Wipe, Wedge Wipe, and Zig-Zag Blocks

EDL Horizontal Split Wipe Stretch Over and Venetian Blind

EDL Inset Inset transition

EDL Vertical Wipe Cube Spin, Pinwheel, Push, Roll Away, Slide, Sliding Boxes, Stretch, Swing In, Swing Out, and Wipe

EDL Vertical Split Wipe Band Slide, Band Wipe, Barn Doors, Doors, Sliding Bands, Spin, Spin Away, and Split

Video switchers interpret wipe patterns as codes. You can associate the wipe patterns in the EDL with the wipe pattern codes used by your postproduction facility by clicking Wipe Codes in the EDL Output dialog box (see “Exporting an EDL” on page 362). Consult with your postproduction facility to determine the wipe codes that are used by their switchers.

 *You may want to create an EDL from a simplified copy of your project, so that your postproduction facility can easily use the EDL. To simplify the project, remove clips from the Video 2 or higher tracks and use only supported transitions and effects.*

Components of an EDL

While slight differences exist among different EDLs, most contain eight primary columns, two auxiliary columns, and the following information:

Header Names the list and the type of timecode in which the record was created (drop-frame or non-drop-frame).

Event Number Identifies a single *event* or edit. You can use the event number to locate a specific edit while fine-tuning the program on the online system. Certain events may use more than one line of the EDL. Unnumbered lines accompanying events are called *notes* or *comments*.

Source Reel ID Identifies the name or number of the videotape containing the clip.

Edit Mode Indicates whether the edits take place on the video track only (V), the audio track only (A), or a combination of both (B).

Transition Type Describes the type of edit: *C* represents a cut, *W* represents a wipe, *K* represents a key (superimposed), and *D* represents a dissolve.

Source In and Source Out Lists the timecode of the first frame and the last frame of the clip as it appears on the source videotape.

Program In and Program Out Lists the timecode at which the source clip is to be recorded on the master tape.

A									
TITLE: SAFARI									
FCM: NON-DROP FRAME									
001	003	U	C		00:00:03:12	00:00:05:14	01:00:20:01	01:00:22:03	
001	004	U		W001 204	00:00:06:24	00:00:12:23	01:00:08:12	01:00:14:11	
EFFECTS NAME IS SWING IN									
002	004	U	C		01:16:22:03	01:16:29:02	01:00:06:24	01:00:13:25	
002	001	U		W003 204	01:18:27:15	01:18:34:09	01:00:06:24	01:00:13:18	
EFFECTS NAME IS SWING IN									
003	004	U	C		01:18:33:15	01:00:25:14	01:00:13:18	01:00:20:12	
003	001	U		W000 204	01:18:38:02	01:18:44:26	01:00:13:18	01:00:20:12	
EFFECTS NAME IS SWING IN									
004	004	U	C		01:19:10:02	01:19:15:03	01:19:20:12	01:19:25:12	
004	001	U		W002 204	01:19:23:19	01:19:30:13	01:00:20:12	01:00:27:06	
EFFECTS NAME IS SWING IN									
005	004	U	C		01:34:12:02	01:34:16:04	01:00:22:05	01:00:26:06	
005	001	U		W011 203	01:50:15:29	01:50:22:22	01:00:27:06	01:00:33:29	
EFFECTS NAME IS ZOOM									
006	003	U	C		01:52:14:25	01:52:16:05	01:00:33:29	01:00:35:15	
007	001	U	C		01:39:08:00	01:39:14:24	01:00:58:15	01:01:05:09	
B	C	D	E		F		G		

A. Header B. Event Number C. Source Reel ID D. Edit Mode E. Transition Type F. Source In and Source Out G. Program In and Program Out

Audio in the EDL

Because Premiere works with files on a computer instead of tapes, it controls sound in a way that differs significantly from traditional editing systems. Traditional tape-based editing systems are designed to record from (and to) one or more audio tracks on the videotape or onto a separate audio tape recorder. Premiere provides up to 99 audio tracks in the Timeline for placement of audio clips; however, when you play or export video, Premiere produces a single track that can contain more than one channel (such as left and right). In Premiere, mixing of audio tracks is controlled by the fade and pan controls that accompany each audio track. The standard EDL has no way to mix sound, except for the mixing that occurs when one audio source dissolves into another audio source.

To take advantage of multiple audio tracks on videotape, you can define which audio tracks from Premiere are mapped to the available tracks in the editing system. The following options are available when you choose an EDL option from the bottom of the File > Export Timeline menu (except Generic EDL) and click the Audio Mapping button (see “Exporting an EDL” on page 362):

Audio Follows Video Causes the audio and video to be listed together, according to the edits made on the video track: where the video cuts, the linked audio clip cuts; where the video fades, the linked audio fades; and so on. Premiere processes the video edits, processes the audio to match, and lists the result in the EDL. The audio fade and pan controls are ignored.

Audio Separately Interleaves the audio and video tracks as separate edits within the EDL. For these options, the following rules govern the way that Premiere translates sound edits into a format that the EDL can interpret:

- If a clip on track Video 1A completely overlaps a clip on track Video 1B (that is, if it has the same or an earlier In point and the same or a later Out point), only the clip on track Video 1A is considered.

Note: A fade point of 0 in any clip effectively splits the clip at that point so that the clip is treated as two clips by the EDL.

- If a clip on track Video 1A and a clip on track Video 1B overlap, a transition is created in the overlapping area so that the starting clip fades in to the ending clip.
- Clips on superimpose tracks are considered only when neither track Video 1A nor track Video 1B contains clips; otherwise, they are ignored.

Once this single “track” has been created, the EDL interprets fade points in the following way:

- A fade point of 0 in any nontransition area creates a fade between 0 at that point and 100 at the next nearest point specified in the clip, regardless of the actual value that was specified for the nonzero point. All other nonzero fade points are ignored.
- Fade points in any *transition* areas (that is, areas of clips on tracks Video 1A and Video 1B that overlap) are ignored.

Audio at End Lists all the sound edits together at the end of the EDL, using the same audio translation rules as the Audio Separately option.

Index

A

- A/B Editing workspace 8, 9, 67, 73, 169, 242
 - A/B roll editing 169, 364
 - action-safe zones 277
 - Add Clip to Project command 152
 - Adjusting audio levels in the Timeline 257
 - Adobe Acrobat Reader 1
 - Adobe After Effects
 - effects 70, 332
 - exporting to 346
 - importing from 155
 - Adobe Certification program 5
 - Adobe Dimensions 155
 - Adobe Illustrator (AI) file format
 - empty areas as transparent 302
 - importing as animation 155
 - importing as still image 153, 154
 - maximum image size 154
 - Adobe Online 3, 4
 - Adobe Photoshop
 - editing video frames in 349
 - importing from 155
 - using alpha channel from 302
 - Adobe Photoshop (PSD) file format 155
 - importing 153
 - importing as animation 155
 - layers in 155
- Adobe Premiere
 - keyboard shortcuts 198
 - new features 49
 - Adobe Web site 3
 - Advanced RealMedia Export 47, 54
 - Advanced Settings 76
 - After Effects. *See* Adobe After Effects
 - AI. *See* Adobe Illustrator (AI) file format
 - AIF, AIFF file format 151, 338
 - alignment 281
 - Alpha Channel key 43, 302
 - alpha channels
 - from Photoshop 155
 - in motion settings 318
 - premultiplied 302
 - previewing by scrubbing 231
 - straight 302
 - in titles 291
 - using in Premiere 302
 - Alpha Glow effect 332
 - Alpha Glow effect. *See online Help*
 - analog media
 - capture checklist 110
 - defined 109
 - anamorphic aspect ratio 148, 149
 - Animated GIF file format 338, 345
 - animation
 - defined 155
 - effects 39, 329
 - importing 155
 - keyframes, and 323
 - stop-frame 139
 - using motion controls 44, 311
 - animation. *See also* motion
 - Anti-alias effect 332
 - Anti-alias effect. *See online Help*
 - anti-aliasing 154, 249
 - Apply button 182
 - Apply Default Transition button 247
 - archiving 83
 - ASF Intelligent Streaming 47
 - aspect ratio 51, 77, 147
 - anamorphic 148
 - D1 147

- D4/D16 149
- DV 147
- for pixels 78
- maintaining original 196
- square pixels 149
- attenuating audio 256
- audio 144
 - adjusting levels automatically in the Audio Mixer 266
 - audio lead edit 261
 - Audio Mixer 263
 - automating mixing 59
 - balancing 262
 - bit depth 78, 144
 - boosting 332
 - Capture Settings 144
 - capturing 144
 - changing dynamic range 332
 - channels, ganging 58
 - chorus effect 332
 - clipping 263
 - controlling delay and modulation 332
 - cross-fading 203, 260
 - cross-fading clips linked to video 260
 - delay 332
 - digital audio tape 145
 - echo 332
 - editing 255
 - effects, descriptions of each. *See online Help*
 - Enhanced Rate Conversion 79
 - equalization 332
 - expanding an audio track 257
 - fade adjustment tool 259
 - fade scissors tool 259
 - fading 34, 359
 - fading in the Audio Mixer 34, 266
 - fading in the Timeline 34, 257
 - formats 78, 358
 - gain 256
 - Ignore Audio Rubber Bands option 360
 - importing digital 145
 - in EDLs 364, 368
 - interleaving 79, 359
 - inverting phase of signal 332
 - J-cut edit 261
 - L-cut edit 261
 - linking with video 219
 - Logarithmic Audio Fades 79
 - mixing 34, 263
 - mixing in the Audio Mixer 263
 - MP3 format 344
 - nonlinear fades 268
 - panning 36, 60, 262, 332
 - panning in the Audio Mixer 36, 264, 269
 - panning in the Timeline 36, 262
 - playing 35
 - preview or playback sample rate 78
 - preview vs. playback 79
 - processing order 255
 - project settings 78
 - removing background noise 332
 - removing extreme frequencies 332
 - removing hum 332
 - resampling 79, 359
 - reverberation 332
 - selecting tracks for playback 268
 - setting In and Out points 183
 - specifying codec 79
 - split edit 261
 - suppressing effects 80, 360
 - tracks 58, 263
 - tracks in EDLs 365
 - unganging audio tracks 268
 - using left or right channel only 270
 - viewing clips 271
 - volume 256
 - VU meter 59
 - working with Audio Mixer 263

- Audio button 119
- audio capture 119, 144, 145
 - sample rate 144
 - sample rate (Mac OS) 145
- Audio Capture command 144
- Audio Gain command 256
- audio lead 261
- Audio Mixer, transport controls 264
- audio preview 78
- Audio Settings
 - for exporting 358
 - for previewing or playback 78
- Audio workspace 8, 36, 68, 170
- Auto Pan effect 332
- Auto Pan effect. *See online Help*
- Autodesk Animation file format. *See Flc/Fli file format*
- Automate to Timeline command 24, 64, 202, 205, 241
- Automation Off option 59, 264
- Automation Read option 264
- Automation Write option 35, 59, 264
- autosaving 83
- AVC file format. *See DPS Perception*
- AVI file format 151
- B**
- background clip, title 275
- background mattes 306
- Backwards (audio) effect. *See online Help*
- Backwards effect 332
- backwards, playing a clip 192, 195
- balancing audio 36, 262
- Basic 3D effect 332
- Basic 3D effect. *See online Help*
- Bass & Treble effect 332
- Bass & Treble effect. *See online Help*
- batch capturing 51, 130
 - defined 130
- batch lists
 - capturing video from 136
 - defined 130
 - handles 135
 - managing 134
 - settings 135
- Batch Processing command 351
- Bend effect 332
- Bend effect. *See online Help*
- Bevel Alpha effect 332
- Bevel Alpha effect. *See online Help*
- Bevel Edges effect 332
- Bevel Edges effect. *See online Help*
- bin view 61
 - adding and deleting containers in 92
 - displaying contents 93
 - hiding and displaying 92
 - resizing 92
- Bin window
 - deleting items 98
 - finding items 98
- bins 15
 - Bin View 61
 - creating new 61
 - defined 92
 - exporting a file list from 99
 - naming 97
 - renaming 98
- bit depth 144
 - audio 78, 144, 358
 - color 77, 357
 - for export 357
 - video 77
- Black & White effect 332
- Black & White effect. *See online Help*
- Black Alpha Matte key 303
- Block Move Marker option 173
- block select tool 225
- Blue Screen key type 301
- blurring images 332
- BMP file format 155, 338
 - importing 153
- Boost effect 332
- Boost effect. *See online Help*
- Brightness & Contrast effect 332

- Brightness & Contrast effect. *See online Help*
- Bring to Front command 291
- Broadcast Colors effect 332
- Broadcast Colors effect. *See online Help*
- B-roll, creating in EDL 364
- burned-in timecode 143

- C**
- Camera Blur effect 332
- Camera Blur effect. *See online Help*
- Camera View effect 332
- Camera View effect. *See online Help*
- Capture settings
 - audio 144
 - overview 74, 118
 - specific to particular video-capture cards 125
- Capture window 52
- capturing 52
 - analog video 113
 - audio. *See* audio capture
 - batch capturing 130
 - checklists for 110
 - with device control 127
 - without device control 125
 - DV 114, 120
 - settings for 118
 - single frames 139
 - stop-motion 139
 - timecode 142
- CD. *See* compact disc audio
- CD-ROM, creating video for 345, 354
- Center Horizontally command 291
- Center Vertically command 291
- centering
 - clip on motion path 314
 - title objects 291
 - title paragraph 281
- Change Speed option 216
- Channel Mixer effect 332
- Channel Mixer effect. *See online Help*
- channels
 - ee also* tracks
 - ganging 58
 - inverting 332
 - mixing 332
 - muting one channel of stereo clip 270
 - pan control 60
 - reversing in stereo clip 271
 - using left or right stereo channels only 270
 - VU meter 59
- channels (images), defined 302
- Schapter link 185, 189
- Chorus effect 332
- Chorus effect. *See online Help*
- Chroma key type 300
- Cinepak, cropping video at export 361
- Classroom in a Book 5
- Clip effect 332
- Clip effect. *See online Help*
- Clip window 151, 152
 - controllers 57
 - printing contents 98
- clipping in audio 263
- clips 332
 - adding multiple automatically 202
 - adding multiple to Source view 164
 - adding to superimpose track 42
 - adding to Timeline 199
 - animating 311
 - applying effects to 328
 - blending 301
 - blurring 332
 - breaking into tiles 332
 - brightness, adjusting 332
 - centering, on motion path 314
 - contrast, adjusting 332
 - copying settings to other clips 216
 - creating subclips 184
 - cropping pixels 332
 - cutting and pasting 216

- darkening 332
- data rate analysis of 157
- deleting 98
- deleting space between 217
- displaying 164
- distorting 44, 315, 316, 317
- distorting along a curve 332
- duration 191, 209
- editing 26
- editing linked clips individually 220
- editing original 189
- enabling and disabling for output 196
- excluding from EDL 196
- finding source 197
- flat areas, creating 332
- flipping 332
- frame rate 193
- getting info on 101
- halting 332
- handling space between 203
- head, defined 222
- importing 151
- instances 184
- linking video and audio clips 218
- locking and unlocking 197
- logging 132
- marking In and Out points 181
- masking 302
- master 184
- mosaic pattern 332
- motion and 311
- motion settings speed 314
- moving in time 208
- moving with Sync mode 56
- naming 97
- nesting edits 223
- opening 152, 164
- organizing in project 15, 92
- organizing in Timeline 223
- outlining edges 332
- panning audio 262
- Paste Attributes command 216, 217
- pixel aspect ratio 147
- playing in reverse 167, 191, 192
- poster frame 60, 96
- previewing 80, 222
- properties of 157
- relinking 220
- removing all on one track 218
- removing effects from 329
- renaming 98
- replicating 332
- resizing 44, 190, 332
- ripple patterns 332
- rolling (as on a surface) 332
- rotating 44, 315, 316
- scaling 190, 332
- selecting 207
- selecting multiple 207
- setting order and placement for Timeline 202
- sharpening 332
- simulating texture 332
- size 190
- snapping to markers 209
- specifying source and target tracks 178
- speed 191
- splitting 215
- subclips 184
- superimposing 306
- tail, defined 222
- three-dimensional effect 332
- tiling 332
- trimming 26, 220
- trimming unused frames 86
- twirling 332
- using bins to organize 15
- using storyboard for 24
- viewing audio waveform 271
- viewing effects in 40
- viewing in Project window 15

- viewing video 164
- virtual clips 223
- zooming 316
- clips, effects in
 - halo 332
 - lightening 332
 - replacing colors 332
 - trimming pixels 332
 - trimming pixels from edges 332
 - viewing 40
- clutter in Timeline, reducing 172
- CMX format 362
- codecs 353
 - cross-platform 87
 - for exporting 353, 357
 - for audio playback 79
 - for playback 76
 - for previewing 76
 - Type option 359
- color. *See* colors 332
- Color Balance (HLS) effect 332
- Color Balance (HLS) effect. *See online Help*
- Color Balance effect 332
- Color Balance effect. *See online Help*
- color depth. *See* bit depth, color
- Color Emboss effect 332
- Color Emboss effect. *See online Help*
- color gamut, defined 290
- color keys 43
- Color Offset effect 332
- Color Offset effect. *See online Help*
- color palettes 77, 357
- Color Pass effect 332
- Color Pass effect. *See online Help*
- color picker, using 290
- Color Replace effect 332
- Color Replace effect. *See online Help*
- colors
 - adjustments with Channel Mixer effect 332
 - balance 332
 - bit depth 357
 - breaking into dots 332
 - corrections 332
 - corrections, contrast 332
 - eliminating noise around transitions between 332
 - for playback 77
 - gamut warning 290
 - guidelines for using in broadcast video 332
 - hand-tinted images 332
 - in Extract effect 332
 - inverting 332
 - matching in the Title window 287
 - motion background 318
 - picking for titles 290
 - replacing 332
 - replacing one with another throughout 332
 - setting outside clip 196
 - swapping object and shadow colors 288
 - tinting clips 332
- Commands palette 64, 102
- comments 188
- compact disc audio 145
- composites 42
 - See also* superimposing clips
- compositing. *See* transparency
- compression
 - Data Rate Analyzer and 157
 - for exporting 359, 360
 - final video settings 353
 - for playback 76, 81, 338
 - for previewing 76, 81
- compression keyframes 80, 81, 158, 355
- Compressor option 76
- compressor. *See* codecs
- Compressor/Expander effect 332
- Compressor/Expander effect. *See online Help*
- Configure option 76
- Constant option 332
- controllers 18
 - activating 166

- buttons 167
- ganging 232
- Program view 19
- Source View 19
- synchronizing 232, 233
- convolution 195
- Convolution Kernel effect 332
- Convolution Kernel effect. *See online Help*
- Copy command 216
- corrections 89
 - See also* History palette
- counting leader 61, 227
- crawling titles 282
- Crop effect 332
- Crop effect. *See online Help*
- cropping
 - pixels from edges of clips 332
 - when exporting 361
- cross-application editing 69
- cross-fade tool 260
- cross-fading 260
 - defined 257
- cross-platform projects 87
- Crystallize effect 332
- Crystallize effect. *See online Help*
- Current Settings 76
- current time marker. *See* edit line
- Cut command 216
- cutaways 200
- cuts, defined 239
- D**
- D1 footage 147, 150
 - aspect ratio 147
- D1/DV NTSC 149
 - Widescreen 149
- D1/DV PAL 149
 - Widescreen 149
- D4/D16
 - Anamorphic 149
 - footage, aspect ratio 149
 - Standard 149
- darkening images 332
- DAT. *See* digital audio tape (DAT)
- data rate
 - analyzing 157
 - CD-ROM playback 354
 - defined 353
 - export limit 358
 - intranet 354
 - for playback 354
 - preview or playback limit 78
 - videotape, recording to 354
 - World Wide Web 354
- default transition 246
- defaults, setting
 - still image duration 153
 - title attributes 279, 284
 - transition 246
 - transition settings 248
- deinterlacing 195, 361
- delay, motion option 45
- deleting
 - clips 98, 217
 - range of frames 217
 - source files 86
 - space between clips 217
- depth. *See* bit depth
- device control 51
 - capturing with 127
 - capturing without 125
 - defined 127
 - plug-ins 128
 - recording to videotape 341
- difference frames 158
- Difference Matte key type 304
- DigiSuite cards 228
- digital audio tape (DAT) 145
- digital audio, importing 145
- digital media, defined 109
- digital video. *See* DV
- digitizing
 - defined 109
 - See also* capturing
- Dimensions. *See* Adobe Dimensions
- Directional Blur effect 332

- Directional Blur effect. *See online Help*
- distorted lens effect 332
- distorting a clip 315, 316, 317
- documentation overview 1
- dots, creating illusion of 332
- DPS Perception 151
- Draft option (Title window) 278
- Drop Shadow effect 332
- Drop Shadow effect. *See online Help*
- dropped frames
 - aborting capture on 119
 - identifying clips with 157
 - preventing 120
 - reporting during capture 119
- Dual View 18, 163, 167, 169, 222
- Duplicate Left command 270
- Duplicate Right command 270
- duration
 - changing clip 209
 - clip 191
 - defined 191
 - still image default 153
 - Timeline marker 188
- Duration command 191
- Duration, marker option 188
- DV
 - connecting video source 112
 - device control 51, 127
 - digitizing analog as 113
 - file interchange options 51
 - frame movie mode 81
 - nonsquare pixel support 51
 - online editing 111
 - preparing for capture 120
 - presets 11, 50, 61
 - project settings 11
 - timecode 114
- DV footage
 - aspect ratio 147
 - using 147
- DV NTSC 150
- DV stream 51
- E**
- Echo (audio) effect 332
- Echo (audio) effect. *See online Help*
- Echo (video) effect 332
- Echo (video) effect. *See online Help*
- edge trim tool 181
- edges, highlighting in Find Edges
 - effect 332
- Edit at Razor Line command 215
- edit decision lists (EDLs)
 - audio and 364, 365, 368
 - defined 111
 - exporting 362
 - generating 362
 - parts of 367
 - recording reel options 363
 - special effects in 365
 - timebase and 363
- edit line
 - about 176
 - moving 176
- Edit Original command 69, 189
- edit, defined 168
- editing
 - adding clip to the Timeline 199
 - audio 255
 - audio lead edit 261
 - cancelling 222
 - clip duration 191, 209
 - clip frame rate 193
 - clip speed 191
 - cross-application 69
 - cutting and pasting clips 216
 - four-point edit 205
 - In and Out points 180
 - with the keyboard 198
 - L-cut edit 181, 260, 261
 - with Monitor controllers 166
 - moving clips in time 208
 - nesting edits 223
 - nonlinear fades 268
 - offline 111
 - online 111

- online with DV 111
- original file 69, 189
- previewing 222
- range of frames 217
- removing clips or range of frames 217
- ripple edit 28, 210, 213
- ripple edit using Trim view 221
- rolling edit 29, 210, 212
- rolling edit using Trim view 221
- slide edit 212, 214
- slip edit 211, 214
- specifying source and target tracks 178
- split edit 181, 260, 261
- splitting a clip 215
- subclips and 184
- three-point edit 205
- with the Timeline 171
- trimming 220
- trimming unused frames 86
- viewing a clip 164
- Editing mode 75
- EDL. *See* edit decision lists
- E-E mode 114
- Effect Controls palette 40, 66
- Effect Enabled button 325
- Effect Keyframe track 66
- effects 66
 - accessing replaced Premiere effects 332
 - adjusting 39
 - animating 39, 323
 - applying 38, 65, 328
 - audio. *See also individual effect names*
 - changing settings at a keyframe 330
 - copying (with keyframes) and pasting to another clip 328
 - EDLs and 366
 - Effect Controls palette 66
 - Effect Keyframe track 66
 - folder management 65
 - from Adobe After Effects 70, 332
 - keyframes 40, 323
 - obsolete 70, 332
 - palettes 40, 326
 - plug-ins 332
 - removing from clip 329
 - setting keyframes 39
 - suppressing for export 360
 - suppressing for preview or playback 41, 80
 - turning off 329
 - video. *See also individual effect names*
 - viewing 38
- Effects palette 328
- Effects workspace 8, 68, 170
- ellipse tool 284
- Emboss effect 332
- Emboss effect. *See online Help*
- Enhanced Rate Conversion 79, 359
- Equalize effect 332
- Equalize effect. *See online Help*
- excluding tracks 176
- Export Clip command 343
- Export to Tape command 341, 342
- exporting 337, 347
 - Advanced RealMedia Export 47, 54
 - audio settings 358
 - batch processing 351
 - compression 353, 359, 360
 - cropping frames during 361
 - EDLs 362
 - field settings 360
 - file formats 352
 - file types for 352
 - frame rate 357
 - frame size 357
 - keyframe and rendering settings 359
 - keyframes for 355
 - limiting data rate 358
 - Media Cleaner Export 47

- for motion-picture film 361
 - noise reduction 361
 - optimizing still images 360
 - to other software 346
 - overview 46
 - plug-ins 47, 53
 - Quality option 358
 - QuickTime (MOV) 47, 53
 - Recompress option 358
 - Save for Web plug-in 47, 53
 - scaling video to frame size 361
 - settings 75, 352
 - Special Processing 360, 361
 - still-image sequence 348
 - text list of files 99
 - to the Web 47, 53
 - using CD-ROM optimized plug-in 347
 - using Premiere's export function 347
 - using Web plug-in 347
 - video 337
 - video settings 357
 - Windows Media Export 47, 53, 54
- Extract button 218
- Extract effect 332
- Extract effect. *See online Help*
- extracting, defined 217
- F**
- Facet effect 332
- Facet effect. *See online Help*
- fade adjustment tool 259, 297
- fade control 296
- fade scissors tool 259, 297
- fading
- adding fade handles 34
 - audio 34, 59, 256, 266
 - audio, nonlinear fades 268
 - in the Timeline 34
 - video 296
 - with the Audio Mixer 34
- Fast Blur effect 332
- Fast Blur effect. *See online Help*
- field
- dominance 194
 - recreating missing 332
 - settings 81, 360
 - See also* interlaced video fields 332
- Field Interpolate effect 332
- Field Interpolate effect. *See online Help*
- file formats 151, 352
- files
- finding 61
 - missing 85
 - offline 85, 158
 - size limitations 116
 - temporary 88
 - using large files in Mac OS 116
 - using large files in Windows 116
 - See also* clips 85
- Fill Left and Fill Right effects 332
- Fill Left and Fill Right effects. *See online Help*
- film, motion-picture 76, 111, 361
- filmstrip 349
- Filmstrip (FLM) file format 155, 338, 349
- filters. *See* effects
- Find Edges effect 332
- Find Edges effect. *See online Help*
- Find icon, Project window 98
- finding files 61
- FireWire 49
- FireWire/i.Link 120
- Flanger effect 332
- Flanger effect. *See online Help*
- Flc/Fli file format 155, 338
- Flicker Removal option 195
- flicker, reducing 81, 195, 332
- flipping images 332
- FLM. *See* Filmstrip (FLM) file format
- Font command (Title window) 280
- fonts
- See also* Adobe Type Library and Adobe Type Manager

- titles, and 280
- footage. *See* clips
- four-point editing 205, 206
- frame aspect ratio 147
- frame blending, defined 193
- Frame Hold command
 - applying 194
 - freezing a frame with 197
- frame movie mode 81
- frame rate
 - for capturing 119
 - clip 193
 - for exporting 357
 - for playback 77
 - for previewing 77
- frame size 11
 - for capturing 119
 - for exporting 357
 - for playback 77
 - for previewing 77
- frames
 - cropping at export 361
 - difference 158
 - dropped, identifying clips with 157
 - freezing 195, 197
 - marking 180, 185
 - navigating 167
 - navigating with shuttle slider and jog tread 168
 - painting 349
 - poster 15
 - replacing 205
 - trimming unused 86
 - See also* frame rate and frame size
 - freezing a frame 195
 - function keys, assigning commands 103
- G**
- gain
 - adjusting 256
 - adjusting in the Timeline 34
 - using Logarithmic Audio Fades to control 79
- Gain command 256
- gamma adjustment 361
- Gamma Correction effect 332
- Gamma Correction effect. *See online Help*
- gamut warning 290
- gang button, Monitor window 233
- garbage mattes 307
- Gaussian Blur effect 332, 333
- Gaussian Blur effect. *See online Help*
- Gaussian Sharpen effect 332
- Gaussian Sharpen effect. *See online Help*
- General preferences 3
- General settings 74, 75, 347, 348
- Ghosting effect 332
- Ghosting effect. *See online Help*
- GIF file format
 - See also* Animated GIF file format
 - importing 153
- GIF sequence 338
- gradients, in a title 288
- Graphics Interchange Format. *See* GIF file format
- graphics, in titles 284
 - setting default attributes 284
- Grass Valley format 362
- grayscale images 332
- Green Screen key type 301
- H**
- halo effect, creating 332
- handles, batch list 135
- headroom, defined 144
- Help 2
- High Pass effect 332
- High Pass effect. *See online Help*
- hinted movie 344
- History palette 70, 89, 104
- Horizontal Flip effect 332
- Horizontal Flip effect. *See online Help*
- Horizontal Hold effect 332
- Horizontal Hold effect. *See online Help*

I

icons

- changing size 205
- in storyboards 204

IEEE 1394 49, 112, 120

Ignore Audio Filters option 80, 360

Ignore Audio Rubber Bands option 80, 360

Ignore Video Filters option 80, 360

iLink 49

Illustrator. *See* Adobe Illustrator (AI) file format

Image Mask transition 250

Image Matte key 303

Image Pan effect. *See online Help*

images

- blurring 332
- darkening 332
- grayscale 332
- hand-tinted 332
- reflecting 332
- sepia-tone 332

importing

- animations 155
- clips 21, 151
- compact disc audio 145
- digital audio 145
- file formats 151
- folders 151, 152

multiple clips 152

numbered sequences 155

projects 156

still images 153

video clips 152

In points

- defined 163
- editing in program 209
- editing in Timeline 182
- finding 182
- for program 166
- for source 166
- marking and finding 181
- setting at a frame or sample 183
- setting between timebase divisions 183
- three- or four-point edits and 205

Info palette 101

Insert button 206

Insert button (for source clip) 201

inserting clip in program 199

interlaced video fields 195

- processing a clip with 194
- Reverse Field Dominance option 195
- See also* fields

Interleave option 79, 359

Internet, creating video for 343

Interpret Footage command 193

intranet, data rate for 354

Invert effect 332

Invert effect. *See online Help*

J

J-cut edit 261

jog tread 168

JPEG, JPG (Joint Photographics Experts Group) file format importing 153

Justify command 281

K

kerning, title text 281

key types

- Alpha Channel 302
- Black Alpha Matte 303
- Blue Screen 301
- Chroma 300
- Difference Matte 304
- Green Screen 301
- Image Matte 303
- Luminance 302
- Multiply 302
- None 299
- Non-Red 301
- RGB Difference 300
- Screen 302
- Track Matte 305
- White Alpha Matte 303

- See also* transparency 298
- keyboard shortcuts 198
 - See also Quick Reference Card*
- keyframe and rendering options
 - defined 74
 - for exporting 359
 - for playback 80
- keyframe icons 325
- Keyframe line 324
- keyframe navigator 325
- keyframes 66
 - creating at edits 360
 - creating at markers 360
 - creating for export 360
- keyframes, compression 158
 - evaluating data rate for 158
 - options for 81, 360
 - setting 355
- keyframes, effect 323
 - defined 323
 - moving edit line 330
 - removing 41, 331
 - repositioning 331
 - selecting 330
 - setting 39
 - using 329
 - using for animation 39
- keyframes, motion 312, 313, 314, 316, 318
 - deleting 314
 - keying (keying out), defined 295
 - keys
 - applying 298
 - compositing and 295
 - defined 295
 - in EDLs 363
 - See also* key types 364
- L**
 - layers from Photoshop files 155
 - L-cut edit 181, 260, 261
 - leader, counting 227
 - Leading command 281
 - Lens Distortion effect 332
 - Lens Distortion effect. *See online Help*
 - Lens Flare effect 332
 - Lens Flare effect. *See online Help*
 - Levels effect 332
 - Levels effect. *See online Help*
 - libraries, importing 94
 - Lift button 217
 - lifting, defined 217
 - lightening images 332
 - line spacing, in titles 281
 - Line Weight option 285
 - linking video and audio 218, 219, 261
 - links
 - chapter 189
 - Web 188
 - List view fields 96
 - Load Palette Now 77
 - Load Project Settings 10
 - lock icon 180
 - lock track icon 16
 - locking
 - clips 197
 - tracks 180
 - Logarithmic Audio Fades option 79, 268, 359
 - logging clips for batch capturing 130, 132
 - looping playback 167
 - Low Pass effect 332
 - Low Pass effect. *See online Help*
 - Luminance key type 302
- M**
 - Mac OS, moving projects to 87
 - Macintosh Picture file format. *See* PICT
 - Macintosh Sound Format 151
 - Magnify icon 177
 - Make Palette from Movie option 77, 357
 - Marker Menu button 276
 - markers 188
 - adding comments 188

- chapter link 54, 189
- deleting 187
- duration 188
- for frame rendering 80
- going to 186
- marking sample title frame 275
- setting 186
- Show Markers option 172
- snapping clips to 209
- Timeline 188
- using 185
- Web link 54
- masks
 - alpha channel 302
 - Image Mask transition 250
- master clip, defined 184
- mattes
 - background 306
 - color 306
 - creating temporary, for keying 306
 - defined 303
 - garbage 307
 - moving 305
 - Track matte 305
- Media Cleaner Export 47, 337
- Median effect 332
- Median effect. *See online Help*
- menus, displaying 14
- Microsoft AVI 338
- Microsoft Windows, moving projects to 87
- Mirror effect 332
- Mirror effect. *See online Help*
- missing files 158
- mistakes
 - correcting 89
 - See also* undo
- mixing. *See* audio
- Monitor window 12
 - adding a clip using 201
 - comments 188
 - controllers for 18, 166
 - customizing 166
 - defined 90
 - Dual View 18
 - moving the edit line using 176
 - new features 61
 - overview 18
 - Single View 18
 - synchronizing controllers 232
 - Trim mode 19
 - using 163
 - views 18
- monitors. *See* previewing
- Monochrome option 332
- monophonic sound balancing 36
- Mosaic effect 332
- Mosaic effect. *See online Help*
- motion 44
 - accelerating 317
 - background fill for 318
 - centering a clip 314
 - decelerating 317
 - default path 44
 - defining a path for 44, 312
 - delaying 45, 317
 - deleting keyframes on path 314
 - distorting a clip 317
 - fine-tuning position 313
 - loading settings for 319
 - moving matte 305
 - previewing settings for 315
 - replacing static background behind moving object 304
 - rotating a clip 45, 316
 - settings in EDLs 366
 - settings, editing 314
 - slow 195
 - smoothing 317
 - smoothing motion, rotation, distortion 315
 - speed and 314
 - superimposing 318
 - synchronizing 317
 - timeline 44
 - transparency and 315, 318
 - zooming 316

- Motion command 44, 311, 312, 314
- motion path 311
- Motion Picture Experts Group.
See MPEG file format
- motion-picture film 361
 - plug-ins 362
- MOV. See QuickTime (MOV)
- movie analysis. See properties, clips
- Movie Capture command 126, 128
- Movie command. See exporting
- MP3 audio 47, 344
- MPEG file format 344
- MPEG-1 47
- Multi-Effect effect 332
- Multi-Effect effect. See *online Help*
- Multiply key type 302
- multirazor tool 215
- Multitap Delay effect 332
- Multitap Delay effect. See *online Help*
- multitrack select tool 173, 207, 208
- Mute control 58
- Mute Left command 270
- Mute Right command 270
- muting 270
- N**
- Navigator palette 102, 176
- nesting 223
- new features in Premiere 49
- New Project command 10
- Noise effect 332, 333
- Noise effect. See *online Help*
- Noise Gate effect 332
- Noise Gate effect. See *online Help*
- Noise Reduction option (video) 361
- None key type 299
- noninterlaced video 194
- Non-Red key type 301
- nonsquare pixel support 51
- Notch/Hum effect 332
- Notch/Hum effect. See *online Help*
- NTSC 147, 149
 - signals 339
 - timebase for 76
- NTSC-safe colors 278
- Numbered Stills option 156
- O**
- obsolete effects 332
 - See also *online Help*
- offline editing
 - about 111
 - defined 111
- offline files 85, 158
- On Insert option 172
- online editing, defined 111
- online Help 2
- Online Settings preference 4
- opacity 296
- opacity, titles 287
 - See also transparency
- Open dialog box 85
- Open DML file format 151
- opening
 - clips 164
 - projects 85
- Optimize Stills option 80, 360
- Orientation command (titles) 281
- Out points
 - defined 163
 - editing in program 209
 - editing in Timeline 182
 - finding 182
 - finding and marking 181
 - for program 166
 - for source 166
 - three- or four-point edits and 205
- output
 - See also exporting
- Overlay button 201, 206
- overscan, defined 165, 277
- P**
- page peel icon 43
- painting frames 349
- PAL video 148, 149

- timebase 76
- palette menu, displaying 14
- palettes 12
 - arranging 14
 - displaying 13
 - displaying in different workspaces 169, 170
 - docking 101
 - effects 326
 - grouping 101
 - Info 101
 - moving and separating 101
 - saving positions 170
 - showing and hiding 100
 - using 91, 100
- pan control 60, 262
- Pan effect 332
- Pan effect. *See online Help*
- panning audio 36, 262, 264, 332
 - in the Audio Mixer 36
 - in the Timeline 36
 - with Auto Pan effect 332
- Parametric Equalization effect 332
- Parametric Equalization effect. *See online Help*
- Paste Attributes command 216, 217
- Paste to Fit command 216
- PCX file format, importing 153
- PDF, viewing with Acrobat Reader 1
- Perception. *See* DPS Perception
- Photoshop. *See* Adobe Photoshop
- PICT file format
 - exporting as sequence 338
 - importing as sequence 155
 - importing as still image 153
- picture-in-a-picture effect 249
- Pinch effect 332
- Pinch effect. *See online Help*
- pixel aspect ratio 149
 - defined 147
 - setting 150
- pixels
 - aspect ratio 78
 - changing brightness values of 332
 - increasing contrast in adjacent 332
 - nonsquare 51
 - trimming from edges of clips 332
- placeholders 158
- playback settings 76, 77
 - compression 81
- playing back
 - backward 195
 - full-screen 235
 - looping 167
- Monitors window and 167
 - selecting audio tracks 268
 - speed 167
- plug-ins
 - device control 128
 - editing modes 75
 - effects 332
- Pointillize effect 332
- Pointillize effect. *See online Help*
- Polar Coordinates effect 332
- Polar Coordinates effect. *See online Help*
- polygon tool 284
- polygons in titles 284
- poster frame 15, 60, 96, 204, 275
- Posterize effect 332
- Posterize effect. *See online Help*
- Posterize Time effect 332
- Posterize Time effect. *See online Help*
- postroll 167
- preferences
 - Auto Save/Undo 84
 - general 3
 - scratch disks 88, 234
 - startup window 100
 - temp files 88
- premultiplication 154
- preroll 120, 167
- presets 10, 61, 74
- preview files 233

- deleting 234
 - specifying location for 234
- Preview from RAM option 232
- Preview to Screen option 231
- previewing 32
 - at final playback speed 230
 - on black screen 235
 - building preview (including effects) 33
 - by scrubbing 231
 - color coding of previews 56
 - compression 81
 - controls 19
 - from Disk 80
 - from RAM 80, 232
 - in real time 228
 - motion 315
 - on another monitor 233
 - overview 228
 - preview files 230, 233
 - Quality option 78
 - render-scrub 245
 - rolling or crawling titles 283
 - single clip 32
 - synchronizing controllers in 232
 - to Screen 80, 231
 - via scrubbing 230
 - video program (without effects) 32
- Print to Video command 235, 343
- printing windows 98
- program
 - defined 163
 - previewing 228
 - recording on videotape 339
 - video 163, 199
- program clip, defined 163
- Program controller 19
- Program view 18
 - controller 19, 166
- progressive downloadable video 344
- project settings 11, 74
 - Advanced Settings 76
 - changing 11
 - comparing 82
 - Current Settings 76
 - Custom 11
 - Editing Mode 75
 - playback 76
 - saving and loading 82
 - Time Display 76
 - timebase 76
 - Video Settings 76
- Project Settings command 11
- Project Trimmer command 86
- Project window 12, 14
 - bin view 92
- bins 15
 - customizing 94
 - defined 90
 - deleting items 98
 - exporting a file list 99
 - finding items 97
 - importing clips into 152
 - printing contents 98
 - sorting footage 15
 - viewing footage 15
- Project-Archive folder 84
- projects
 - archives 84
 - autosaving 83
 - defined 73
 - General Settings 74, 75
 - importing 156
 - keyframe and rendering options 74
 - moving to another platform 87
 - opening 85
 - presets 74
 - starting 73
 - trimming clips 86
 - Video Settings 74
- Properties window 157
- properties, clips 157
- PSD. *See* Adobe Photoshop file format

PVD. *See* DPS Perception

Q

Quality option

for exporting 358

for previewing 78

Quick Reference Card 2

QuickTime (MOV)

editing mode 75

exporting 47, 53, 338, 344,
357

flattened movies 338

importing 151

markers 54

QuickTime Streaming 343

R

Radial Blur effect 332

Radial Blur effect. *See online Help*

RAM

previewing from 232

using for previewing 80

range select tool 207

rasterizing Adobe Illustrator files
154

rate stretch tool 192

razor tool 215

RealMedia export 54, 338

RealMedia SureStream 47

RealVideo, RealG2Streaming 343

Recompress option 78, 358

rectangle tool 284

rectangular pixels 148

Reduce icon 177

Reduce Interlace Flicker effect 332

Reduce Interlace Flicker effect. *See
online Help*

Reel Time 228

reference card 2

referenced movie 116

refraction, simulating 332

registering 1

Remove Background Clip
command 277

Remove Unused Clips command
98

renaming

bins 98

clips 98

Render Work Area command 230

rendering 33, 74, 230

See also previewing

frames with markers 80

render-scrubbing 33, 51, 245

See also previewing 245

Replicate effect 332

Replicate effect. *See online Help*

resampling 79, 359

Resize effect 332

Resize effect. *See online Help*

resizing

clip 45

clip in Timeline 190

Reverb effect 332

Reverb effect. *See online Help*

Reverse Field Dominance option
195

reverse, playing clips in 167, 192

Revert command, History palette
and 104

RGB

images, defined 302

levels, controlling in clips 332

RGB Difference key type 300

Ripple Delete command 217

ripple deletion 217

ripple edit 28, 210

using Trim view 221

ripple edit tool 28, 213

Ripple effect 332

Ripple effect. *See online Help*

Roll effect 332

Roll effect. *See online Help*

rolling edit 29, 210

using Trim view 221

rolling edit tool 30, 212

Rolling Title Options command
282

rolling title tool 282

rolling titles 282

rotating a clip 315, 316

rotoscoping 349

- rough cuts, online 111
- rounded-corner rectangle tool 284
- rubberband
 - adjusting audio levels 257
 - defined 257
 - fading audio 257
 - fading video 296
 - panning audio 262
- S**
- safe zones
 - action-safe 165, 277
 - changing 166
 - defined 165
 - overscan 277
 - title-safe 165, 277
 - viewing in Monitor window 165
- sample rate
 - audio capture 144
 - audio capture (Mac OS) 145
 - audio preview or playback 78
 - exporting 359
- Save a Copy command 84
- Save As command 84
- Save command 84
- Save for Web export plug-in 47, 53
- Save Workspace command 8
- scaling clip in Timeline 190
- scissors, fade tool 259, 297
- scratch disks 88, 144
 - defined 88
- Scratch Disks/Device Control
 - command 234, 341, 342
- Screen key type 302
- scrubbing 33, 245
 - defined 230
 - render-scrub 231
- SECAM, timebase 76
- Send to Back command 291
- sepia-tone images 332
- sequences of still frames 155, 348
- Set Clip Name Alias command 97
- settings
 - copying from one clip to another 216
 - export 75, 352, 355
 - for capture 74
 - guidelines 75
 - online 4
 - pixel aspect ratio 149
 - project 11
 - viewing 62
- Settings Viewer 62, 82
- shadows
 - Drop Shadow effect 332
 - in titles 286
 - specifying in Emboss effect 332
- Sharpen Edges effect 332
- Sharpen Edges effect. *See online Help*
- Sharpen effect 332
- Sharpen effect. *See online Help*
- Shear effect 332
- Shear effect. *See online Help*
- Shift Material in All Tracks option 219
- Shift Material in All Unlocked Tracks option 172
- Shift Material Only in Target Tracks option 172, 219
- Shift Tracks button 16, 56
- Show Audio Effects command 328
- Show Tool Tips option 3
- Show Video Effects command 328
- shuttle slider, in Monitor window 168
- shy tracks 175
- Single View 18, 163, 167, 169, 170
- Single-Track Editing mode 169
- Single-Track Editing workspace 8, 16, 67, 73
 - adding transitions 244
- Size command 281
- Skip All option 85
- Skip option 85
- Skip Preview Files option 85
- slide edit 212
- slide tool 214

- slip edit 211
 - slip tool 214
 - slow motion 195
 - Smooth Polygon command 286
 - Snap to Edges command 209
 - soft link tool 219
 - Solarize effect 332
 - Solarize effect. *See online Help*
 - Solo control 58
 - Sony BVE format 362
 - Sound Designer I & II file formats 151
 - Sound Recorder, Windows 144
 - source clip 163
 - defined 163
 - finding 197
 - source files, deleting 86
 - Source View 18
 - controller 19, 166
 - menu 164
 - time display 164
 - Special Processing export options 360, 361
 - Speed command 192
 - speed, clip 191, 314
 - Spherize effect. *See online Help*
 - split edits 181, 260, 261
 - split points 181
 - split-screen 308
 - splitting a clip 215
 - square pixels 148, 149, 150
 - startup window 100
 - stereo sound balancing 36
 - still images
 - Adobe Illustrator and 154
 - Adobe Photoshop and 155
 - aspect ratio of 196
 - duration of 153
 - exporting sequence 348
 - importing 153
 - numbered sequence 156
 - optimizing 80
 - optimizing at export 360
 - as sample title frame 275
 - Stop Motion command 139
 - stop-frame animation 139
 - storyboard 24
 - Automate to Timeline, and 205
 - creating 204
 - defined 204
 - History palette and 104
 - importing image 153
 - new features 63
 - playing contents 235
 - printing contents 98
 - Storyboard window
 - about 63
 - defined 202
 - streaming video 343, 354
 - strobe effect 332
 - Strobe Light effect 332
 - Strobe Light effect. *See online Help*
 - Style command 281
 - subclips 184
 - creating 184
 - marking In and Out points for 183
 - superimpose tracks 16
 - superimposing clips 42, 306
 - adding superimpose tracks 42
 - EDLs and 365
 - Superimpose track 171
 - titles 279
 - See also* transparency
 - Swap Channels command 271
 - Swap Left & Right effect 332
 - Swap Left & Right effect. *See online Help*
 - Sync mode 208, 218
 - Sync Mode button 56
 - synchronization
 - corrections 124
 - motion settings 317
- T**
- Take Audio icon 179
 - Take Video icon 179

- Targa (TGA) file format 338
 - importing 153
- target track 20, 178
- targeting 20
- temp files 88
 - defined 88
 - setting up 88
- text. *See* titles
- Texturize effect 332
- Texturize effect. *See online Help*
- TGA. *See* Targa (TGA) file format
- three-dimensional effects 332
- three-point editing 10, 205
- thumbnail viewer 96
- thumbnail views 92
 - sorting 95
- TIFF, TIF
 - exporting as sequence 338
 - importing as sequence 155
 - importing as still image 153
- Tiles effect 332
- Tiles effect. *See online Help*
- Time Display option 76
- time ruler 176
- Time Units menu 17, 177
- timebase
 - creating EDLs and 363
 - setting for project 76
- timecode
 - burned-in 143
 - capturing 142
 - maintaining continuity 114
 - offset 120
 - setting manually 143
- Timeline count 172
- visual 143
- Timecode command 362
- Timecode effect 332
- Timecode effect. *See online Help*
- timecode log 130
- time-lapse. *See* capturing
 - stop-motion
- Timeline 23, 26, 172
 - adding clips 23, 199
 - customizing 172
 - defined 90
 - Fade icon (audio) 17
 - Fade icon (video) 17
 - Keyframe icon 17
 - magnifying and reducing 102
 - markers 185
 - navigating 171
 - new features 56
 - Pan icon 17
 - printing contents 98
 - recording with device control 341
 - recording without device control 342
- Time Zoom Level menu 17
- Timeline menu 57
 - using 171
- Waveform icon 17
- zooming 177
- Timeline menu 57
- Timeline window 12, 16
- Timeline Window Options
 - command 172
- time-vary stopwatch, defined 325
- Tint effect 332
- Tint effect. *See online Help*
- tinted images 332
- Title window 275
 - History palette and 104
- titles
 - adding to a project 291
 - alignment of text in 281
 - alpha channels in 291
 - arranging text and graphics in 290
 - background, making transparent 292
 - centering 281
 - centering objects 291
 - color matching 287
 - color picker 290
 - crawling 282
 - creating 275
 - cross-platform 87

- defined 275
- Draft option 278
- editing text in 280
- filled objects 285
- filled or framed objects 284, 285
- fonts 280
- framed objects 285
- gradients in 288
- graphics in 284
- Justify command 281
- kerning text in 281
- line spacing (leading) 281
- line weight 285
- opacity 292
- Orientation command 281
- polygons in 284, 286
- previewing rolling or crawling 283
- rolling 282
- rotating 281
- sample frame for positioning 275
- selecting tools for 278
- setting default attributes for 279, 284
- shadows in 286
- stacking text and graphics 290
- stretching type in 281
- Title window options and 277
- title-safe zones 277
- Toggle Edge Viewing button 16
- Toggle Snap to Edges command 16
- Toggle Sync Mode button 16, 171, 208, 218
- tonal range, remapping pixels in channel 332
- Tool Tips 198
- tools
 - hidden 13
 - selecting 13
 - See also individual tool names* 13
- Track Matte key type 305
- Track Mode button 173
- tracks 20, 172
 - adding and deleting 56, 177
 - adding to Timeline 178
 - audio 58
 - audio in EDLs 365
 - customizing view 173
 - excluding from output 176
 - expanding all 17
 - expanding audio 257
 - format options 172
 - ganging 35
 - hiding in Timeline 175
 - locking and unlocking 180
 - multitrack select tool 173
 - naming 177
 - removing all clips on 218
 - resizing track heading section 174
 - selecting for audio playback 268
 - Shift Tracks button 56
 - shy 175
 - superimpose 16, 295
 - targeting 178
 - Transitions 243
 - Transform effect. *See online Help*
 - Transition Settings command 248
- transitions 16, 30
 - about 239
 - adding 30, 241
 - anti-aliasing 249
 - applying 65
 - Border slider 249
 - center point 249
 - changing settings 248
 - combining 242
 - cut 239
 - default 31, 241
 - default settings 248
 - default transition 246
 - defined 239
 - descriptions of each. *See online Help*
 - in EDLs 364, 365
 - Image Mask 250

- in A/B Editing workspace 242
 - in Single-Track Editing workspace 243
 - orientation 249
 - picture-in-a-picture effect 249
 - playing forward or backward 249
 - previewing 243
 - replacing 56, 247
 - settings 248
 - smoothness of edges 249
 - starting and ending frames of 248
 - track 31
 - Zoom 249
- Transitions palette 31, 239
- transparency 295
- adding clip to superimpose track 42
 - applying 43
 - Key menu 43
 - motion and 44, 303, 315, 318
 - preparing for 42
 - superimposing clips 306
 - See also* key types 302
- Transparency command 292, 298
- transport controls 264
- traveling matte, defined 305
- Trim mode 19, 163, 222
- Trim Source option 216
- Trim view 220
- options 222
 - ripple edit 221
 - rolling edit 221
- trimming
- edge trim tool 181
 - pixels from edges of clips 332
 - ripple edit 28
 - rolling edit 29
 - unused frames 86
 - using Trim view 220
 - See also* editing 86
- Twirl effect 332
- Twirl effect. *See online Help*
- Type option for audio codec 359
- type tool 279
- type. *See* titles
- U**
- undo 89
- using History palette 70
- Unlink Audio and Video command 219
- usage, video and audio 97
- using in D1 or DV project 150
- V**
- vertical convolution 195
- Vertical Flip effect 332
- Vertical Flip effect. *See online Help*
- Vertical Hold effect 332
- Vertical Hold effect. *See online Help*
- video
- capturing from batch list 136
 - effects, descriptions of each. *See online Help*
 - effects, obsolete 332
 - exporting 337, 347
 - fading 296
 - interlaced 194
 - linking with audio 219
 - noninterlaced 194
 - progressive downloadable 344
 - recording final 339
 - streaming 343
 - suppressing effects 80
- Video button, capture setting 119
- Video for Windows 75
- Video Settings
- defined 74
 - specifying for previews 76
- video-capture cards 117
- videotape
- data rate for 354
 - device control and 341
 - recording to 235, 338, 339
- virtual clips 223
- locating original frames 226
- visual timecode 143

volume
 adjusting 257
 See also fading, audio
 Volume Fader 35, 59
 volume fader 257
 volume rubberband 257
 volumes, defined 88
 VU meter 59

W

WAV (Windows Audio
 Waveform) file format 151,
 338
 Wave effect 332
 Wave effect. *See online Help*
 Web export 47, 53
 Web link 185, 188
 markers 54
 Web site for Adobe 4
 White Alpha Matte key 303
 Wind effect 332

Wind effect. *See online Help*
 window dub timecode, setting
 manually for a clip 143
 window menus
 displaying 14
 using 91
 Windows Audio Waveform. *See*
 WAV file format
 Windows Bitmap file format. *See*
 BMP file format
 Windows Media 338
 Windows Media Export 47, 53,
 54
 windows, Premiere 100, 170, 171
 WindowsMedia 343
 wipe codes 364
 work area 12, 225, 229, 347
 workflow 109
 workspace 8
 A/B Editing 8, 9, 67, 73, 169
 Audio 8, 68, 170

 choosing 169
 defined 67
 Effects 8, 68, 170
 managing 170
 selecting initial 73
 Single-Track Editing 8, 16, 67,
 73, 169
 World Wide Web 343, 354

Z

Zig Zag effect 332
 ZigZag effect. *See online Help*
 zones. *See* safe zones
 zoom tool 177
 Zoom transition 249
 zooming 177, 190, 316